



Cisco Secure Firewall Management Center Snort 3 Configuration Guide, Version 7.4

First Published: 2023-09-07

Last Modified: 2024-05-03

Americas Headquarters

Cisco Systems, Inc.
170 West Tasman Drive
San Jose, CA 95134-1706
USA
<http://www.cisco.com>
Tel: 408 526-4000
800 553-NETS (6387)
Fax: 408 527-0883

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

All printed copies and duplicate soft copies of this document are considered uncontrolled. See the current online version for the latest version.

Cisco has more than 200 offices worldwide. Addresses and phone numbers are listed on the Cisco website at www.cisco.com/go/offices.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: <https://www.cisco.com/c/en/us/about/legal/trademarks.html>. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1721R)

© 2023–2024 Cisco Systems, Inc. All rights reserved.



CONTENTS

CHAPTER 1

An Overview of Network Analysis and Intrusion Policies 1

- About Network Analysis and Intrusion Policies 1
- Snort Inspection Engine 2
- Snort 3 2
- Snort 2 versus Snort 3 4
- Feature Limitations of Snort 3 for Management Center-Managed Threat Defense 5
- How Policies Examine Traffic For Intrusions 6
 - Decoding, Normalizing, and Preprocessing: Network Analysis Policies 6
 - Access Control Rules: Intrusion Policy Selection 7
 - Intrusion Inspection: Intrusion Policies, Rules, and Variable Sets 8
 - Intrusion Event Generation 10
- System-Provided and Custom Network Analysis and Intrusion Policies 10
 - System-Provided Network Analysis and Intrusion Policies 11
 - Benefits of Custom Network Analysis and Intrusion Policies 12
 - Benefits of Custom Network Analysis Policies 13
 - Benefits of Custom Intrusion Policies 13
 - Limitations of Custom Policies 14
- Prerequisites for Network Analysis and Intrusion Policies 16

CHAPTER 2

Migrate from Snort 2 to Snort 3 17

- Snort 3 Inspection Engine 17
- Prerequisites for Network Analysis and Intrusion Policies 18
- How to Migrate from Snort 2 to Snort 3 18
 - Prerequisites for Migrating from Snort 2 to Snort 3 18
 - Enable Snort 3 on an Individual Device 19
 - Enable Snort 3 on Multiple Devices 19

- Convert Snort 2 Custom IPS Rules to Snort 3 20
 - Convert all Snort 2 Custom Rules across all Intrusion Policies to Snort 3 20
 - Convert Snort 2 Custom Rules of a Single Intrusion Policy to Snort 3 21
- View Snort 2 and Snort 3 Base Policy Mapping 21
- Synchronize Snort 2 Rules with Snort 3 22
- Deploy Configuration Changes 23

PART I

Intrusion Detection and Prevention in Snort 3 25

CHAPTER 3

Get Started with Snort 3 Intrusion Policies 27

- Overview of Intrusion Policies 27
- Prerequisites for Network Analysis and Intrusion Policies 28
- Create a Custom Snort 3 Intrusion Policy 28
 - Edit Snort 3 Intrusion Policies 29
 - Rule Group Reporting 32
 - Rule Action Logging 33
- Change the Base Policy of an Intrusion Policy 33
- Manage Intrusion Policies 34
- Access Control Rule Configuration to Perform Intrusion Prevention 35
 - Access Control Rule Configuration and Intrusion Policies 35
 - Configure an Access Control Rule to Perform Intrusion Prevention 35

CHAPTER 4

Tune Intrusion Policies Using Rules 37

- Overview of Tuning Intrusion Rules 37
- Intrusion Rule Types 38
- Prerequisites for Network Analysis and Intrusion Policies 39
- Custom Rules in Snort 3 39
- View Snort 3 Intrusion Rules in an Intrusion Policy 42
- Intrusion Rule Action 42
 - Intrusion Rule Action Options 42
 - Set Intrusion Rule Action 43
- Intrusion Event Notification Filters in an Intrusion Policy 43
 - Intrusion Event Thresholds 44
 - Set Intrusion Event Thresholds 44

Set Threshold for an Intrusion Rule in Snort 3	45
View and Delete Intrusion Event Thresholds	46
Intrusion Policy Suppression Configuration	46
Intrusion Policy Suppression Types	46
Set Suppression for an Intrusion Rule in Snort 3	47
View and Delete Suppression Conditions	47
Add Intrusion Rule Comments	48
Snort 2 Custom Rules Conversion to Snort 3	48
Convert all Snort 2 Custom Rules across all Intrusion Policies to Snort 3	49
Convert Snort 2 Custom Rules of a Single Intrusion Policy to Snort 3	49
Add Custom Rules to Rule Groups	50
Add Rule Groups with Custom Rules to an Intrusion Policy	51
Manage Custom Rules in Snort 3	51
Delete Custom Rules	52
Delete Rule Groups	53

CHAPTER 5

Tailor Intrusion Protection for Your Network Assets	55
Snort 3 Rule Changes in LSP Updates	55
Overview of Secure Firewall Recommended Rules	55
Prerequisites for Network Analysis and Intrusion Policies	56
Generate New Secure Firewall Recommendations in Snort 3	57

PART II

Advanced Network Analysis in Snort 3 61

CHAPTER 6

Get Started with Snort 3 Network Analysis Policies	63
Overview of Network Analysis Policies	63
Manage Network Analysis Policies	64
Snort 3 Definitions and Terminologies for Network Analysis Policy	65
Prerequisites for Network Analysis and Intrusion Policies	67
Custom Network Analysis Policy Creation for Snort 3	67
Common Industrial Protocol Safety	71
Detect and Block Safety Segments in CIP Packets	72
Network Analysis Policy Mapping	72
View Network Analysis Policy Mapping	72

- Create a Network Analysis Policy 73
- Modify the Network Analysis Policy 73
- Search for an Inspector on the Network Analysis Policy Page 74
- Copy the Inspector Configuration 75
- Customize the Network Analysis Policy 75
- Make Inline Edit for an Inspector to Override Configuration 78
- Revert Unsaved Changes during Inline Edits 79
- View the List of Inspectors with Overrides 80
- Revert Overridden Configuration to Default Configuration 80
- Validate Snort 3 Policies 81
- Examples of Custom Network Analysis Policy Configuration 83
- Network Analysis Policy Settings and Cached Changes 94

PART III

Encrypted Visibility Engine for Snort 3 95

CHAPTER 7

Encrypted Visibility Engine 97

- Overview of Encrypted Visibility Engine 97
- How EVE Works 98
- Indications of Compromise Events 98
- QUIC Fingerprinting in EVE 99
- Configure EVE 99
 - View EVE Events 100
 - View EVE Dashboard 101

PART IV

Elephant Flow Detection for Snort 3 103

CHAPTER 8

Elephant Flow Detection 105

- About Elephant Flow Detection and Remediation 105
- Elephant Flow Upgrade from Intelligent Application Bypass 105
- Configure Elephant Flow 106

PART V

Snort 3 Use Cases 109

CHAPTER 9

Migrate from Snort 2 to Snort 3 In Secure Firewall Management Center 111

Migrate from Snort 2 to Snort 3	111
Benefits of Migrating to Snort 3	111
Sample Business Scenario	112
Best Practices for Migrating from Snort 2 to Snort 3	112
Prerequisites	112
End-to-End Migration Workflow	112
Enable Snort 3 on Threat Defense	113
Convert Snort 2 Rules of a Single Intrusion Policy to Snort 3	114
Deploy Configuration Changes	119

CHAPTER 10 **Generate Snort 3 Recommendations In Secure Firewall Management Center** 121

Snort 3 Rule Recommendations	121
Benefits	122
Sample Business Scenario	122
Best Practices	122
Prerequisites	122
Generate Snort 3 Recommendations	122
Deploy Configuration Changes	125

CHAPTER 11 **Block Traffic Based on the EVE Threat Confidence Score** 129

About Encrypted Visibility Engine	129
Benefits	129
Sample Business Scenario	129
Prerequisites	130
High-Level Workflow	130
Configure Block Thresholds in EVE	130
View EVE Events	133
Additional References	134

CHAPTER 12 **Configure Elephant Flow Detection Outcomes** 135

About Elephant Flows	135
Benefits of Elephant Flow Detection and Remediation	135
Elephant Flow Workflow	135
Sample Business Scenario	136

Prerequisites	136
Configure Elephant Flow Parameters	137
View Events for Elephant Flows	139
Configure Elephant Flow Remediation Exemption	140
View Events for Elephant Flow Remediation Exemption	143
Additional References	143

CHAPTER 13	Mitigate Threats Using MITRE Framework in Snort 3 Intrusion Policies	145
	About MITRE Framework	145
	Benefits of MITRE Framework	146
	Prerequisites	146
	Sample Business Scenario	146
	View and Edit Your Snort 3 Intrusion Policy	146
	View Intrusion Events	151
	Additional References	153



CHAPTER 1

An Overview of Network Analysis and Intrusion Policies

The Snort inspection engine is an integral part of the Secure Firewall Threat Defense (formerly Firepower Threat Defense) device. This chapter provides an overview of Snort 3 and the network analysis and intrusion policies. It also provides an insight into system-provided and custom network analysis and intrusion policies.

- [About Network Analysis and Intrusion Policies, on page 1](#)
- [Snort Inspection Engine, on page 2](#)
- [Snort 3, on page 2](#)
- [Snort 2 versus Snort 3, on page 4](#)
- [Feature Limitations of Snort 3 for Management Center-Managed Threat Defense, on page 5](#)
- [How Policies Examine Traffic For Intrusions, on page 6](#)
- [System-Provided and Custom Network Analysis and Intrusion Policies, on page 10](#)
- [Prerequisites for Network Analysis and Intrusion Policies, on page 16](#)

About Network Analysis and Intrusion Policies

Network analysis and intrusion policies work together as part of the intrusion detection and prevention feature.

- The term *intrusion detection* generally refers to the process of passively monitoring and analyzing network traffic for potential intrusions and storing attack data for security analysis. This is sometimes referred to as "IDS."
- The term *intrusion prevention* includes the concept of intrusion detection, but adds the ability to block or alter malicious traffic as it travels across your network. This is sometimes referred to as "IPS."

In an intrusion prevention deployment, when the system examines packets:

- A **network analysis policy** governs how traffic is *decoded* and *preprocessed* so it can be further evaluated, especially for anomalous traffic that might signal an intrusion attempt.
- An **intrusion policy** uses *intrusion and preprocessor rules* (sometimes referred to collectively as *intrusion rules*) to examine the decoded packets for attacks based on patterns. Intrusion policies are paired with *variable sets*, which allow you to use named values to accurately reflect your network environment.

Both network analysis and intrusion policies are invoked by a parent access control policy, but at different times. As the system analyzes traffic, the network analysis (decoding and preprocessing) phase occurs before

and separately from the intrusion prevention (additional preprocessing and intrusion rules) phase. Together, network analysis and intrusion policies provide broad and deep packet inspection. They can help you detect, alert on, and protect against network traffic that could threaten the availability, integrity, and confidentiality of hosts and their data.

The system is delivered with several similarly named network analysis and intrusion policies (for example, Balanced Security and Connectivity) that complement and work with each other. By using system-provided policies, you can take advantage of the experience of the Cisco Talos Intelligence Group (Talos). For these policies, Talos sets intrusion and inspector rule states, as well as provides the initial configurations for inspectors and other advanced settings.

You can also create custom network analysis and intrusion policies. You can tune settings in custom policies to inspect traffic in the way that matters most to you so that you can improve both the performance of your managed devices and your ability to respond effectively to the events they generate.

You create, edit, save, and manage network analysis and intrusion policies using similar policy editors in the web interface. When you are editing either type of policy, a navigation panel appears on the left side of the web interface; the right side displays various configuration pages.

Refer to the videos for additional support and information:

- [Snort 3 Condensed Overview](#)
- [Snort 3 Extended Overview](#)

Snort Inspection Engine

The Snort inspection engine is an integral part of the Secure Firewall Threat Defense (formerly Firepower Threat Defense) device. The inspection engine analyzes traffic in real time to provide deep packet inspection. Network analysis and intrusion policies together utilize the Snort inspection engine's capabilities to detect and protect against intrusions.

Snort 3

Snort 3 is the latest version of the Snort inspection engine, which has vast improvements compared to the earlier version of Snort. The older version of Snort is Snort 2. Snort 3 is more efficient, and it provides better performance and scalability.

Snort 3 is architecturally redesigned to inspect more traffic with equivalent resources when compared to Snort 2. Snort 3 provides simplified and flexible insertion of traffic parsers. Snort 3 also provides new rule syntax that makes rule writing easier and shared object rule equivalents visible.

The other significant changes with Snort 3 are:

- Unlike Snort 2, which uses multiple Snort instances, Snort 3 associates multiple threads with a single Snort instance. This uses less memory, improves Snort reload times, and supports more intrusion rules and a larger network map. The number of Snort threads varies by platform and is the same as the number of Snort 2 instances for each platform. Usage is virtually transparent.
- Snort version per threat defense—The Snort inspection engine is threat defense specific and not Secure Firewall Management Center (formerly Firepower Management Center) specific. Management Center can manage several threat defenses, each with either versions of Snort (Snort 2 and Snort 3). Although the management center's intrusion policies are unique, the system applies Snort 2 or Snort 3 version of

an intrusion policy for intrusion protection depending on the device's selected inspection engine. For more information on the inspection engine on the device, see [Snort 3 Inspection Engine, on page 17](#).

- Decoder rules—Packet decoder rules fire only in the default intrusion policy. The system ignores decoder rules that you enable in other policies.
- Shared object rules—Snort 3 supports some but not all shared object (SO) intrusion rules (rules with a generator ID (GID) of 3). Enabled shared object rules that are not supported do not trigger.
- Multi-layer inspection for Security Intelligence—Snort 2 inspects two layers in multi-layer traffic. Snort 3 detects the innermost IP address regardless of the layer.
- Platform support—Snort 3 requires threat defense 7.0 or later. It is not supported with ASA FirePOWER or NGIPSv.
- Managed Devices—An management center with version 7.0 can simultaneously support version 6.4, 6.5, 6.6, 6.7, and 7.0 Snort 2 threat defenses, and version 7.0 Snort 3 threat defenses.
- Traffic interruption when switching Snort versions—Switching Snort versions interrupts traffic inspection and a few packets might drop during deployment.
- Unified policies—Irrespective of the underlying Snort engine version that is enabled in the managed threat defenses, the access control policies, intrusion policies, and network analysis policies configured in the management center work seamlessly in applying the policies. All intrusion policies in management center version 7.0 and above have two versions available, Snort 2 version and Snort 3 version. The intrusion policy is unified, which means that it has a common name, base policy, and inspection mode, although there are two versions of the policy (Snort 2 version and Snort 3 version). The Snort 2 and the Snort 3 versions of the intrusion policy can be different in terms of the rule settings. However, when the intrusion policy is applied on a device, the system automatically identifies the Snort version enabled on the device and applies the rule settings configured for that version.
- Lightweight Security Package (LSP)—Replaces the Snort Rule Updates (SRU) for Snort 3 next-generation intrusion rule and configuration updates. Downloading updates downloads both the Snort 3 LSP and the Snort 2 SRU.

LSP updates provide new and updated intrusion rules and inspector rules, modified states for existing rules, and modified default intrusion policy settings for management center and threat defense versions 7.0 or above. When you upgrade an management center from version 6.7 or lower to 7.0, it supports both LSPs and SRUs. LSP updates may also delete system-provided rules, provide new rule categories and default variables, and modify default variable values. For more information on LSP updates, see the *Update Intrusion Rules* topic in the latest version of the *Firepower Management Center Configuration Guide*.

- Mapping of Snort 2 and Snort 3 rules and presets—Snort 2 and Snort 3 rules are mapped and the mapping is system-provided. However, it is not a one-to-one mapping. The system-provided intrusion base policies are pre-configured for both Snort 2 and Snort 3, and they provide the same intrusion prevention although with different rule sets. The system-provided base policies for Snort 2 and Snort 3 are mapped with each other for the same intrusion prevention settings. For more information, see [View Snort 2 and Snort 3 Base Policy Mapping, on page 21](#).
- Synchronizing Snort 2 and Snort 3 rule override—When an threat defense is upgraded to 7.0, you can upgrade the inspection engine of the threat defense to the Snort 3 version. Management Center maps all the overrides in the existing rules of the Snort 2 version of the intrusion policies to the corresponding Snort 3 rules using the mapping provided by Talos. However, if there are additional overrides performed after the upgrade or if you have installed a new threat defense of version 7.0, they have to be manually synchronized. For more information, see [Synchronize Snort 2 Rules with Snort 3, on page 22](#).

- Custom intrusion rules—You can create custom intrusion rules in Snort 3. You can also import the custom intrusion rules that exist for Snort 2 to Snort 3. For more information, see [Custom Rules in Snort 3, on page 39](#).
- Rule groups—The management center groups all Snort 3 rules into rule groups. Rule groups are logical groups of rules which provide an easy management interface to enhance rule accessibility, rule navigation, and a better control over the rule group security level.

From management center 7.3.0, rule navigation for several levels of rule groups is supported that provides more flexibility and logical grouping of rules. The MITRE framework is added that enables you to navigate through rules using the MITRE framework. MITRE is just another category of rule groups and are a part of Talos rule groups.



Note See <https://attack.mitre.org> for information about MITRE.

A rule can be part of multiple rule groups, such as multiple MITRE ATT&CK rule groups, a rule category rule group, multiple "asset type" rule groups, a malware campaign, and others. The available rule groups are listed in the intrusion policy editor and can be selected to enhance policies.

With this multi-level hierarchical structure, you can traverse down to the last element, which is the “leaf rule group.” These rule groups contain sets of rules that are related to each other, such as a specific type of vulnerability, a similar target system, or a similar threat category. Rule groups have four security levels associated with them. You can change the security level, add or remove rule groups, and you can change the rule action for rules that match traffic seen on the network. This is done to bring a satisfactory balance between security, performance, and false positive resistance.

To edit a Snort 3 intrusion policy, see [Edit Snort 3 Intrusion Policies, on page 29](#).

For rule group reporting in intrusion events, see [Rule Group Reporting, on page 32](#).

- Switching between Snort 2 and Snort 3 engines—threat defenses that support Snort3 can also support Snort 2. Switching from Snort 3 to Snort 2 is not recommended from the efficacy perspective. However, if a switch is necessary, follow the instructions in [Snort 3 Inspection Engine, on page 17](#).



Important Although you can switch Snort versions freely, intrusion rule changes in one version of Snort will not be updated in the other version automatically. If you change the rule action for a rule in one version of Snort, ensure you replicate the change in the other version before switching the Snort version. System provided synchronization option only synchronizes the changes in the Snort 2 version of the intrusion policy to the Snort 3 version, and not the other way around.

Snort 2 versus Snort 3

Snort 3 is architecturally redesigned to inspect more traffic with equivalent resources when compared to Snort 2. Snort 3 provides simplified and flexible insertion of traffic parsers. Snort 3 also provides new rule syntax that makes rule writing easier and shared object rule equivalents visible.

The table below lists the differences between the Snort 2 and the Snort 3 versions in terms of the inspection engine capabilities.

Feature	Snort 2	Snort 3
Packet threads	One per process	Any number per process
Configuration memory use	Number of processes * x GB	x GB in total; more memory available for packets
Configuration reload	Slower	Faster; one thread can be pinned to separate cores
Rule syntax	Inconsistent and requires line escapes	Uniform system with arbitrary whitespace
Rule comments	Comments only	#, #begin and #end marks; C language style

Additional reference: [Differences between Snort 2 and Snort 3 in Firepower](#).

Feature Limitations of Snort 3 for Management Center-Managed Threat Defense

The following table lists the features that are supported on Snort 2 but not supported on Snort 3 for management center-managed threat defense devices.


Table 1: Feature Limitations of Snort 3

Policy/Area	Features not supported
Access Control Policy	The following application settings: <ul style="list-style-type: none"> • Safe Search • YouTube EDU
Intrusion Policy	<ul style="list-style-type: none"> • Global rule thresholding • Logging configuration: <ul style="list-style-type: none"> • SNMP • SRU rule updates as Snort 3 supports only LSP rule updates
Other features	Event logging with FQDN names

How Policies Examine Traffic For Intrusions

When the system analyzes traffic as part of your access control deployment, the network analysis (decoding and preprocessing) phase occurs before and separately from the intrusion prevention (intrusion rules and advanced settings) phase.

The following diagram shows, in a simplified fashion, the order of traffic analysis in an inline, intrusion prevention and AMP for Networks deployment. It illustrates how the access control policy invokes other policies to examine traffic, and in which order those policies are invoked. The network analysis and intrusion policy selection phases are highlighted.



In an inline deployment (that is, where relevant configurations are deployed to devices using routed, switched, or transparent interfaces, or inline interface pairs), the system can block traffic without further inspection at almost any step in the illustrated process. Security Intelligence, the SSL policy, network analysis policies, file policies, and intrusion policies can all either drop or modify traffic. Only the network discovery policy, which passively inspects packets, cannot affect the flow of traffic.

Similarly, at each step of the process, a packet could cause the system to generate an event. Intrusion and preprocessor events (sometimes referred to collectively as *intrusion events*) are indications that a packet or its contents may represent a security risk.



Tip The diagram does not reflect that access control rules handle encrypted traffic when your SSL inspection configuration allows it to pass, or if you do not configure SSL inspection. By default, the system disables intrusion and file inspection of encrypted payloads. This helps reduce false positives and improve performance when an encrypted connection matches an access control rule that has intrusion and file inspection configured.

Note that for a single connection, although the system selects a network analysis policy before an access control rule as shown in the diagram, some preprocessing (notably application layer preprocessing) occurs after access control rule selection. This does **not** affect how you configure preprocessing in custom network analysis policies.

Decoding, Normalizing, and Preprocessing: Network Analysis Policies

Without decoding and preprocessing, the system could not appropriately evaluate traffic for intrusions because protocol differences would make pattern matching impossible. Network analysis policies govern these traffic-handling tasks:

- **after** traffic is filtered by Security Intelligence
- **after** encrypted traffic is decrypted by an optional SSL policy

- **before** traffic can be inspected by file or intrusion policies

A network analysis policy governs packet processing in phases. First the system decodes packets through the first three TCP/IP layers, then continues with normalizing, preprocessing, and detecting protocol anomalies:

- The packet decoder converts packet headers and payloads into a format that can be easily used by the inspectors and later, intrusion rules. Each layer of the TCP/IP stack is decoded in turn, beginning with the data link layer and continuing through the network and transport layers. The packet decoder also detects various anomalous behaviors in packet headers.
- In inline deployments, the inline normalization preprocessor reformats (normalizes) traffic to minimize the chances of attackers evading detection. It prepares packets for examination by other inspectors and intrusion rules, and helps ensure that the packets the system processes are the same as the packets received by the hosts on your network.
- Various network and transport layers inspectors detect attacks that exploit IP fragmentation, perform checksum validation, and perform TCP and UDP session preprocessing.

Note that some advanced transport and network inspector settings apply globally to all traffic handled by the target devices of an access control policy. You configure these in the access control policy rather than in a network analysis policy.

- Various application-layer protocol decoders normalize specific types of packet data into formats that the intrusion rules engine can analyze. Normalizing application-layer protocol encodings allows the system to effectively apply the same content-related intrusion rules to packets whose data is represented differently, and to obtain meaningful results.
- The Modbus, DNP3, CIP, and s7commplus SCADA inspectors detect traffic anomalies and provide data to intrusion rules. Supervisory Control and Data Acquisition (SCADA) protocols monitor, control, and acquire data from industrial, infrastructure, and facility processes such as manufacturing, production, water treatment, electric power distribution, airport and shipping systems, and so on.
- Several inspectors allow you to detect specific threats, such as Back Orifice, portscans, SYN floods and other rate-based attacks.

Note that you configure the sensitive data inspector, which detects sensitive data such as credit card numbers and Social Security numbers in ASCII text, in intrusion policies.

In a newly created access control policy, one default network analysis policy governs preprocessing for *all* traffic for *all* intrusion policies invoked by the same parent access control policy. Initially, the system uses the Balanced Security and Connectivity network analysis policy as the default, but you can change it to another system-provided or custom network analysis policy. In a more complex deployment, advanced users can tailor traffic preprocessing options to specific security zones, networks, and VLANs by assigning different custom network analysis policies to preprocess matching traffic.

Access Control Rules: Intrusion Policy Selection

After initial preprocessing, access control rules (when present) evaluate traffic. In most cases, the first access control rule that a packet matches is the rule that handles that traffic; you can monitor, trust, block, or allow matching traffic.

When you allow traffic with an access control rule, the system can inspect the traffic for discovery data, malware, prohibited files, and intrusions, in that order. Traffic not matching any access control rule is handled by the access control policy's default action, which can also inspect for discovery data and intrusions.



Note All packets, **regardless** of which network analysis policy preprocesses them, are matched to configured access control rules—and thus are potentially subject to inspection by intrusion policies—in top-down order.

The diagram in [How Policies Examine Traffic For Intrusions, on page 6](#) shows the flow of traffic through a device in an inline, intrusion prevention and AMP for Networks deployment, as follows:

- Access Control Rule A allows matching traffic to proceed. The traffic is then inspected for discovery data by the network discovery policy, for prohibited files and malware by File Policy A, and then for intrusions by Intrusion Policy A.
- Access Control Rule B also allows matching traffic. However, in this scenario, the traffic is not inspected for intrusions (or files or malware), so there are no intrusion or file policies associated with the rule. Note that by default, traffic that you allow to proceed is inspected by the network discovery policy; you do not need to configure this.
- In this scenario, the access control policy's default action allows matching traffic. The traffic is then inspected by the network discovery policy, and then by an intrusion policy. You can (but do not have to) use a different intrusion policy when you associate intrusion policies with access control rules or the default action.

The example in the diagram does not include any blocking or trusting rules because the system does not inspect blocked or trusted traffic.

Intrusion Inspection: Intrusion Policies, Rules, and Variable Sets

You can use intrusion prevention as the system's last line of defense before traffic is allowed to proceed to its destination. Intrusion policies govern how the system inspects traffic for security violations and, in inline deployments, can block or alter malicious traffic. The main function of intrusion policies is to manage which intrusion and preprocessor rules are enabled and how they are configured.

Intrusion and Inspector Rules

An intrusion rule is a specified set of keywords and arguments that detects attempts to exploit vulnerabilities on your network; the system uses an intrusion rule to analyze network traffic to check if it matches the criteria in the rule. The system compares packets against the conditions specified in each rule and, if the packet data matches all the conditions specified in a rule, the rule triggers.

The system includes the following types of rules created by Cisco Talos Intelligence Group (Talos):

- *shared object intrusion rules*, which are compiled and cannot be modified (except for rule header information such as source and destination ports and IP addresses)
- *standard text intrusion rules*, which can be saved and modified as new custom instances of the rule.
- *preprocessor rules*, which are rules associated with inspectors and packet decoder detection options in the network analysis policy. You cannot copy or edit inspector rules. Most inspector rules are disabled by default; you must enable them to use inspectors to generate events and, in an inline deployment, drop offending packets.

When the system processes packets according to an intrusion policy, first a rule optimizer classifies all activated rules in subsets based on criteria such as: transport layer, application protocol, direction to or from the protected network, and so on. Then, the intrusion rules engine selects the appropriate rule subsets to apply to each packet.

Finally, a multi-rule search engine performs three different types of searches to determine if the traffic matches the rule:

- The protocol field search looks for matches in particular fields in an application protocol.
- The generic content search looks for ASCII or binary byte matches in the packet payload.
- The packet anomaly search looks for packet headers and payloads that, rather than containing specific content, violate well-established protocols.

In a custom intrusion policy, you can tune detection by enabling and disabling rules, as well as by writing and adding your own standard text rules. You can also use Cisco recommendations to associate the operating systems, servers, and client application protocols detected on your network with rules specifically written to protect those assets.



Note When there are insufficient packets to process specific traffic against a block rule, the system continues to evaluate the remaining traffic against other rules. If any of the remaining traffic matches a rule which is set to block, then the session is blocked. However, if the system analyses the remaining traffic to be passed, then the traffic status shows pending on the rule which is stuck for want of complete packets.

Variable Sets

Whenever the system uses an intrusion policy to evaluate traffic, it uses an associated *variable set*. Most variables in a set represent values commonly used in intrusion rules to identify source and destination IP addresses and ports. You can also use variables in intrusion policies to represent IP addresses in rule suppressions and dynamic rule states.

The system provides a single default variable set, which is comprised of predefined default variables. Most system-provided shared object rules and standard text rules use these predefined default variables to define networks and port numbers. For example, the majority of the rules use the variable `$HOME_NET` to specify the protected network and the variable `$EXTERNAL_NET` to specify the unprotected (or outside) network. In addition, specialized rules often use other predefined variables. For example, rules that detect exploits against web servers use the `$HTTP_SERVERS` and `$HTTP_PORTS` variables.



Tip Even if you use system-provided intrusion policies, Cisco **strongly** recommends that you modify key default variables in the default set. When you use variables that accurately reflect your network environment, processing is optimized and the system can monitor relevant systems for suspicious activity. Advanced users can create and use custom variable sets for pairing with one or more custom intrusion policies.



Important If you are creating a custom variable set, do not use a number as the first character in a custom variable set name (for example, 3Snort). This will cause Snort 3 validation to fail when you deploy a configuration to threat defense firewall on the management center.

Intrusion Event Generation

When the system identifies a possible intrusion, it generates an *intrusion or preprocessor event* (sometimes collectively called *intrusion events*). Managed devices transmit their events to the management center, where you can view the aggregated data and gain a greater understanding of the attacks against your network assets. In an inline deployment, managed devices can also drop or replace packets that you know to be harmful.

Each intrusion event in the database includes an event header and contains information about the event name and classification; the source and destination IP addresses; ports; the process that generated the event; and the date and time of the event, as well as contextual information about the source of the attack and its target. For packet-based events, the system also logs a copy of the decoded packet header and payload for the packet or packets that triggered the event.

The packet decoder, the preprocessors, and the intrusion rules engine can all cause the system to generate an event. For example:

- If the packet decoder (configured in the network analysis policy) receives an IP packet that is less than 20 bytes, which is the size of an IP datagram without any options or payload, the decoder interprets this as anomalous traffic. If, later, the accompanying decoder rule in the intrusion policy that examines the packet is enabled, the system generates an inspector event.
- If the IP defragmentation preprocessor encounters a series of overlapping IP fragments, the inspector interprets this as a possible attack and, when the accompanying inspector rule is enabled, the system generates an inspector event.
- Within the intrusion rules engine, most standard text rules and shared object rules are written so that they generate intrusion events when triggered by packets.

As the database accumulates intrusion events, you can begin your analysis of potential attacks. The system provides you with the tools you need to review intrusion events and evaluate whether they are important in the context of your network environment and your security policies.

System-Provided and Custom Network Analysis and Intrusion Policies

Creating a new access control policy is one of the first steps in managing traffic flow using the system. By default, a newly created access control policy invokes system-provided network analysis and intrusion policies to examine traffic.

The following diagram shows how a newly created access control policy in an inline, intrusion-prevention deployment initially handles traffic. The preprocessing and intrusion prevention phases are highlighted.



Note how:

- A default network analysis policy governs the preprocessing of *all* traffic handled by the access control policy. Initially, the system-provided *Balanced Security and Connectivity network analysis policy* is the default.
- The default action of the access control policy allows all non-malicious traffic, as determined by the system-provided *Balanced Security and Connectivity intrusion policy*. Because the default action allows

traffic to pass, the discovery feature can examine it for host, application, and user data before the intrusion policy can examine and potentially block malicious traffic.

- The policy uses default Security Intelligence options (global Block and Do Not Block lists only), does not decrypt encrypted traffic with an SSL policy, and does not perform special handling and inspection of network traffic using access control rules.

A simple step you can take to tune your intrusion prevention deployment is to use a different set of system-provided network analysis and intrusion policies as your defaults. Cisco delivers several pairs of these policies with the system.

Or, you can tailor your intrusion prevention deployment by creating and using custom policies. You may find that the inspector options, intrusion rule, and other advanced settings configured in those policies do not address the security needs of your network. By tuning your network analysis and intrusion policies you can configure, at a very granular level, how the system processes and inspects the traffic on your network for intrusions.

System-Provided Network Analysis and Intrusion Policies

Cisco delivers several pairs of network analysis and intrusion policies with the system. By using system-provided network analysis and intrusion policies, you can take advantage of the experience of the Cisco Talos Intelligence Group (Talos). For these policies, Talos provides intrusion and inspector rule states as well as initial configurations for inspectors and other advanced settings.

No system-provided policy covers every network profile, traffic mix, or defensive posture. Each covers common cases and network setups that provide a starting point for a well-tuned defensive policy. Although you can use system-provided policies as-is, Cisco strongly recommends that you use them as the base for custom policies that you tune to suit your network.



Tip Even if you use system-provided network analysis and intrusion policies, you should configure the system's intrusion variables to accurately reflect your network environment. At a minimum, modify key default variables in the default set.

As new vulnerabilities become known, Talos releases intrusion rule updates also known as *Lightweight Security Package* (LSP). These rule updates can modify any system-provided network analysis or intrusion policy, and can provide new and updated intrusion rules and inspector rules, modified states for existing rules, and modified default policy settings. Rule updates may also delete rules from system-provided policies and provide new rule categories, as well as modify the default variable set.

If a rule update affects your deployment, the web interface marks affected intrusion and network analysis policies as out of date, as well as their parent access control policies. You must re-deploy an updated policy for its changes to take effect.

For your convenience, you can configure rule updates to automatically re-deploy affected intrusion policies, either alone or in combination with affected access control policies. This allows you to easily and automatically keep your deployment up-to-date to protect against recently discovered exploits and intrusions.

To ensure up-to-date preprocessing settings, you **must** re-deploy access control policies, which also deploys any associated SSL, network analysis, and file policies that are different from those currently running, and can also update default values for advanced preprocessing and performance options.

Cisco delivers the following network analysis and intrusion policies with the system:

Balanced Security and Connectivity network analysis and intrusion policies

These policies are built for both speed and detection. Used together, they serve as a good starting point for most organizations and deployment types. The system uses the Balanced Security and Connectivity policies and settings as defaults in most cases.

Connectivity Over Security network analysis and intrusion policies

These policies are built for organizations where connectivity (being able to get to all resources) takes precedence over network infrastructure security. The intrusion policy enables far fewer rules than those enabled in the Security over Connectivity policy. Only the most critical rules that block traffic are enabled.

Security Over Connectivity network analysis and intrusion policies

These policies are built for organizations where network infrastructure security takes precedence over user convenience. The intrusion policy enables numerous network anomaly intrusion rules that could alert on or drop legitimate traffic.

Maximum Detection network analysis and intrusion policies

These policies are built for organizations where network infrastructure security is given even more emphasis than is given by the Security Over Connectivity policies, with the potential for even greater operational impact. For example, the intrusion policy enables rules in a large number of threat categories including malware, exploit kit, old and common vulnerabilities, and known in-the-wild exploits.

No Rules Active intrusion policy

In the No Rules Active intrusion policy, all intrusion rules, and all advanced settings except intrusion rule thresholds, are disabled. This policy provides a starting point if you want to create your own intrusion policy instead of basing it on the enabled rules in one of the other system-provided policies.



Note Depending on the system-provided base policy that is selected, the settings of the policy vary. To view the policy settings, click the **Edit** icon next to the policy and then click the **Base Policy** drop-down box.

Benefits of Custom Network Analysis and Intrusion Policies

You may find that the inspector options, intrusion rules, and other advanced settings configured in the system-provided network analysis and intrusion policies do not fully address the security needs of your organization.

Building custom policies can improve the performance of the system in your environment and can provide a focused view of the malicious traffic and policy violations occurring on your network. By creating and tuning custom policies you can configure, at a very granular level, how the system processes and inspects the traffic on your network for intrusions.

All custom policies have a base policy, also called a base layer, which defines the default settings for all configurations in the policy. A layer is a building block that you can use to efficiently manage multiple network analysis or intrusion policies.

In most cases, you base custom policies on system-provided policies, but you can use another custom policy. However, all custom policies have a system-provided policy as the eventual base in a policy chain. Because rule updates can modify system-provided policies, importing a rule update may affect you even if you are using a custom policy as your base. If a rule update affects your deployment, the web interface marks affected policies as out of date.

Benefits of Custom Network Analysis Policies

By default, one network analysis policy preprocesses all unencrypted traffic handled by the access control policy. That means that all packets are decoded and preprocessed according to the same settings, regardless of the intrusion policy (and therefore intrusion rule set) that later examines them.

Initially, the system-provided Balanced Security and Connectivity network analysis policy is the default. A simple way to tune preprocessing is to create and use a custom network analysis policy as the default.

Tuning options available vary by inspector, but some of the ways you can tune inspectors and decoders include:

- You can disable inspectors that do not apply to the traffic you are monitoring. For example, the HTTP Inspect inspector normalizes HTTP traffic. If you are confident that your network does not include any web servers using Microsoft Internet Information Services (IIS), you can disable the inspector option that looks for IIS-specific traffic and thereby reduce system processing overhead.



Note If you disable an inspector in a custom network analysis policy, but the system needs to use that inspector to later evaluate packets against an enabled intrusion or inspector rule, the system automatically enables and uses the inspector although the inspector remains disabled in the network analysis policy web interface.

- Specify ports, where appropriate, to focus the activity of certain inspectors. For example, you can identify additional ports to monitor for DNS server responses or encrypted SSL sessions, or ports on which you decode telnet, HTTP, and RPC traffic.

For advanced users with complex deployments, you can create multiple network analysis policies, each tailored to preprocess traffic differently. Then, you can configure the system to use those policies to govern the preprocessing of traffic using different security zones, networks, or VLANs. (Note that ASA FirePOWER modules cannot restrict preprocessing by VLAN.)



Note Tailoring preprocessing using custom network analysis policies—especially multiple network analysis policies—is an advanced task. Because preprocessing and intrusion inspection are so closely related, you **must** be careful to allow the network analysis and intrusion policies examining a single packet to complement each other.

Benefits of Custom Intrusion Policies

In a newly created access control policy initially configured to perform intrusion prevention, the default action allows all traffic, but first inspects it with the system-provided Balanced Security and Connectivity intrusion policy. Unless you add access control rules or change the default action, all traffic is inspected by that intrusion policy.

To customize your intrusion prevention deployment, you can create multiple intrusion policies, each tailored to inspect traffic differently. Then, configure an access control policy with rules that specify which policy inspects which traffic. Access control rules can be simple or complex, matching and inspecting traffic using multiple criteria including security zone, network or geographical location, VLAN, port, application, requested URL, or user.

The main function of intrusion policies is to manage which intrusion and inspector rules are enabled and how they are configured, as follows:

- Within each intrusion policy, you should verify that all rules applicable to your environment are enabled, and improve performance by disabling rules that are not applicable to your environment. You can specify which rules should drop or modify malicious packets.
- Cisco recommendations allow you to associate the operating systems, servers, and client application protocols detected on your network with rules specifically written to protect those assets.
- You can modify existing rules and write new standard text rules as needed to catch new exploits or to enforce your security policies.

Other customizations you might make to an intrusion policy include:

- The sensitive data preprocessor detects sensitive data such as credit card numbers and Social Security numbers in ASCII text. Note that other inspectors that detect specific threats (back orifice attacks, several portscan types, and rate-based attacks that attempt to overwhelm your network with excessive traffic) are configured in network analysis policies.
- Global thresholds cause the system to generate events based on how many times traffic matching an intrusion rule originates from or is targeted to a specific address or address range within a specified time period. This helps prevent the system from being overwhelmed with a large number of events.
- Suppressing intrusion event notifications and setting thresholds for individual rules or entire intrusion policies can also prevent the system from being overwhelmed with a large number of events.
- In addition to the various views of intrusion events within the web interface, you can enable logging to syslog facilities or send event data to an SNMP trap server. Per policy, you can specify intrusion event notification limits, set up intrusion event notification to external logging facilities, and configure external responses to intrusion events. Note that in addition to these per-policy alerting configurations, you can globally enable or disable email alerting on intrusion events for each rule or rule group. Your email alert settings are used regardless of which intrusion policy processes a packet.

Limitations of Custom Policies

Because preprocessing and intrusion inspection are so closely related, you **must** be careful that your configuration allows the network analysis and intrusion policies processing and examining a single packet to complement each other.

By default, the system uses one network analysis policy to preprocess all traffic handled by managed devices using a single access control policy. The following diagram shows how a newly created access control policy in an inline, intrusion-prevention deployment initially handles traffic. The preprocessing and intrusion prevention phases are highlighted.



Notice how a default network analysis policy governs the preprocessing of *all* traffic handled by the access control policy. Initially, the system-provided Balanced Security and Connectivity network analysis policy is the default.

A simple way to tune preprocessing is to create and use a custom network analysis policy as the default. However, if you disable an inspector in a custom network analysis policy but the system needs to evaluate preprocessed packets against an enabled intrusion or inspector rule, the system automatically enables and uses the inspector although it remains disabled in the network analysis policy web interface.



Note In order to get the performance benefits of disabling an inspector, you **must** make sure that none of your intrusion policies have enabled rules that require that inspector.


An additional challenge arises if you use multiple custom network analysis policies. For advanced users with complex deployments, you can tailor preprocessing to specific security zones, networks, and VLANs by assigning custom network analysis policies to preprocess matching traffic. (Note that ASA FirePOWER cannot restrict preprocessing by VLAN.) To accomplish this, you add custom *network analysis rules* to your access control policy. Each rule has an associated network analysis policy that governs the preprocessing of traffic that matches the rule.



Tip You configure network analysis rules as an advanced setting in an access control policy. Unlike other types of rules, network analysis rules invoke—rather than being contained by—network analysis policies.

The system matches packets to any configured network analysis rules in top-down order by rule number. Traffic that does not match any network analysis rule is preprocessed by the default network analysis policy. While this allows you a great deal of flexibility in preprocessing traffic, keep in mind that all packets, **regardless** of which network analysis policy preprocessed them, are subsequently matched to access control rules—and thus to potential inspection by intrusion policies—in their own process. In other words, preprocessing a packet with a particular network analysis policy does **not** guarantee that the packet will be examined with any particular intrusion policy. You **must** carefully configure your access control policy so it invokes the correct network analysis and intrusion policies to evaluate a particular packet.

The following diagram shows in focused detail how the network analysis policy (preprocessing) selection phase occurs before and separately from the intrusion prevention (rules) phase. For simplicity, the diagram eliminates the discovery and file/malware inspection phases. It also highlights the default network analysis and default-action intrusion policies.



In this scenario, an access control policy is configured with two network analysis rules and a default network analysis policy:

- Network Analysis Rule A preprocesses matching traffic with Network Analysis Policy A. Later, you want this traffic to be inspected by Intrusion Policy A.
- Network Analysis Rule B preprocesses matching traffic with Network Analysis Policy B. Later, you want this traffic to be inspected by Intrusion Policy B.

- All remaining traffic is preprocessed with the default network analysis policy. Later, you want this traffic to be inspected by the intrusion policy associated with the access control policy's default action.

After the system preprocesses traffic, it can examine the traffic for intrusions. The diagram shows an access control policy with two access control rules and a default action:

- Access Control Rule A allows matching traffic. The traffic is then inspected by Intrusion Policy A.
- Access Control Rule B allows matching traffic. The traffic is then inspected by Intrusion Policy B.
- The access control policy's default action allows matching traffic. The traffic is then inspected by the default action's intrusion policy.

Each packet's handling is governed by a network analysis policy and intrusion policy pair, but the system does **not** coordinate the pair for you. Consider a scenario where you misconfigure your access control policy so that Network Analysis Rule A and Access Control Rule A do not process the same traffic. For example, you could intend the paired policies to govern the handling of traffic on a particular security zone, but you mistakenly use different zones in the two rules' conditions. This could cause traffic to be incorrectly preprocessed. For this reason, tailoring preprocessing using network analysis rules and custom policies is an **advanced** task.

Note that for a single connection, although the system selects a network analysis policy before an access control rule, some preprocessing (notably application layer preprocessing) occurs after access control rule selection. This does **not** affect how you configure preprocessing in custom network analysis policies.

Prerequisites for Network Analysis and Intrusion Policies

To allow the Snort inspection engine to process traffic for intrusion and malware analysis, you must have the IPS license enabled for the Threat Defense device.

You must be an Admin user to manage network analysis, intrusion policies, and perform migration tasks.



CHAPTER 2

Migrate from Snort 2 to Snort 3

Starting with Version 7.0, Snort 3 is the default inspection engine for new threat defense deployments with management center. If you are still using the Snort 2 inspection engine, switch to Snort 3 now for improved detection and performance.

Upgrading threat defense to Version 7.2 through 7.6 also upgrades eligible Snort 2 devices to Snort 3. For devices that are ineligible because they use custom intrusion or network analysis policies, manually upgrade to Snort 3 as described here.

Although you can switch individual devices back, you should not. Snort 2 will be deprecated in a future release and will eventually prevent threat defense upgrade.

- [Snort 3 Inspection Engine](#), on page 17
- [Prerequisites for Network Analysis and Intrusion Policies](#), on page 18
- [How to Migrate from Snort 2 to Snort 3](#), on page 18
- [View Snort 2 and Snort 3 Base Policy Mapping](#), on page 21
- [Synchronize Snort 2 Rules with Snort 3](#), on page 22
- [Deploy Configuration Changes](#), on page 23

Snort 3 Inspection Engine

Snort 3 is the default inspection engine for newly registered threat defense devices of version 7.0 and later. However, for threat defense devices of lower versions, Snort 2 is the default inspection engine. When you upgrade a managed threat defense device to version 7.0 or later, the inspection engine remains on Snort 2. To use Snort 3 in upgraded threat defenses of version 7.0 and later, you must explicitly enable it. When Snort 3 is enabled as the inspection engine of the device, the Snort 3 version of the intrusion policy that is applied on the device (through the access control policies) is activated and applied to all the traffic passing through the device.

You can switch Snort versions when required. Snort 2 and Snort 3 intrusion rules are mapped and the mapping is system-provided. However, you may not find a one-to-one mapping of all the intrusion rules in Snort 2 and Snort 3. If you change the rule action for one rule in Snort 2, that change is not retained if you switch to Snort 3 without synchronizing Snort 2 with Snort 3. For more information on synchronization, see [Synchronize Snort 2 Rules with Snort 3](#), on page 22.

Prerequisites for Network Analysis and Intrusion Policies

To allow the Snort inspection engine to process traffic for intrusion and malware analysis, you must have the IPS license enabled for the Threat Defense device.

You must be an Admin user to manage network analysis, intrusion policies, and perform migration tasks.

How to Migrate from Snort 2 to Snort 3

Migrating from Snort 2 to Snort 3 requires you to switch the inspection engine of the threat defense device from Snort 2 to Snort 3.

Depending on your requirements, the tasks to complete the migration of your device from Snort 2 to Snort 3 is listed in the following table:

Step	Task	Links to Procedures
1	Enable Snort 3	<ul style="list-style-type: none"> • Enable Snort 3 on an Individual Device, on page 19 • Enable Snort 3 on Multiple Devices, on page 19
2	Convert Snort 2 custom rules to Snort 3	<ul style="list-style-type: none"> • Convert all Snort 2 Custom Rules across all Intrusion Policies to Snort 3, on page 20 • Convert Snort 2 Custom Rules of a Single Intrusion Policy to Snort 3, on page 21
3	Synchronize Snort 2 rules with Snort 3	Synchronize Snort 2 Rules with Snort 3 , on page 22

Prerequisites for Migrating from Snort 2 to Snort 3

The following are the recommended prerequisites that you must consider before migrating your device from Snort 2 to Snort 3.

- Have a working knowledge of Snort. To learn about the Snort 3 architecture, see [Snort 3 Adoption](#).
- Back up your management center. See [Backup the Management Center](#).
- Back up your intrusion policy. See [Exporting Configurations](#).
- Clone your intrusion policy. To do this, you can use an existing policy as the base policy to create a copy of your intrusion policy. In the **Intrusion Policies** page, click **Create Policy** and choose an existing intrusion policy from the **Base Policy** dropdown list.

Enable Snort 3 on an Individual Device



Important During the deployment process, there could be a momentary traffic loss because the current inspection engine needs to be shut down.

Step 1 Choose **Devices > Device Management**.

Step 2 Click the device to go to the device home page.

Note The device is marked as Snort 2 or Snort 3, showing the current version on the device.

Step 3 Click the **Device** tab.

Step 4 In the Inspection Engine section, click **Upgrade**.

Note In case you want to disable Snort 3, click **Revert to Snort 2** in the Inspection Engine section.

Step 5 Click **Yes**.

What to do next

Deploy the changes on the device. See, [Deploy Configuration Changes, on page 23](#).

The system converts your policy configurations during the deployment process to make them compatible with the selected Snort version.

Enable Snort 3 on Multiple Devices

To enable Snort 3 on multiple devices, ensure all the required threat defense devices are on version 7.0 or later.



Important During the deployment process, there could be a momentary traffic loss because the current inspection engine needs to be shut down.

Step 1 Choose **Devices > Device Management**.

Step 2 Select all the devices on which you want to enable or disable Snort 3.

Note The devices are marked as Snort 2 or Snort 3, showing the current version on the device.

Step 3 Click **Select Bulk Action** drop-down list and choose **Upgrade to Snort 3**.

Step 4 Click **Yes**.

What to do next

Deploy the changes on the device. See, [Deploy Configuration Changes, on page 23](#).

The system converts your policy configurations during the deployment process to make them compatible with the selected Snort version.

Convert Snort 2 Custom IPS Rules to Snort 3

If you are using a rule set from a third-party vendor, contact that vendor to confirm that their rules successfully convert to Snort 3 or to obtain a replacement rule set written natively for Snort 3. If you have custom rules that you have written yourself, familiarize with writing Snort 3 rules prior to conversion, so you can update your rules to optimize Snort 3 detection after conversion. See the links below to learn more about writing rules in Snort 3.

- <https://blog.snort.org/2020/08/how-rules-are-improving-in-snort-3.html>
- <https://blog.snort.org/2020/10/talos-transition-to-snort-3.html>

You can refer to other blogs at <https://blog.snort.org/> to learn more about Snort 3 rules.

See the following procedures to convert Snort 2 rules to Snort 3 rules using the system-provided tool.

- [Convert all Snort 2 Custom Rules across all Intrusion Policies to Snort 3, on page 20](#)
- [Convert Snort 2 Custom Rules of a Single Intrusion Policy to Snort 3, on page 21](#)

**Important**

Snort 2 network analysis policy (NAP) settings *cannot* be copied to Snort 3 automatically. NAP settings have to be manually replicated in Snort 3.

Convert all Snort 2 Custom Rules across all Intrusion Policies to Snort 3

Step 1 Choose **Objects > Intrusion Rules**.

Step 2 Click **Snort 3 All Rules** tab.

Step 3 Ensure **All Rules** is selected in the left pane.

Step 4 Click the **Tasks** drop-down list and choose:

- **Convert Snort 2 rules and import**—To automatically convert all the Snort 2 custom rules across all the intrusion policies to Snort 3 and import them into management center as Snort 3 custom rules.
- **Convert Snort 2 rules and download**—To automatically convert all the Snort 2 custom rules across all the intrusion policies to Snort 3 and download them into your local system.

Step 5 Click **OK**.

Note

- If you selected **Convert and import** in the previous step, then all the converted rules are saved under a newly created rule group **All Snort 2 Converted Global** under **Local Rules**.
- If you selected **Convert and download** in the previous step, then save the rules file locally. You can review the converted rules in the downloaded file and later upload them by following the steps in [Add Custom Rules to Rule Groups, on page 50](#).

Refer to the video [Converting Snort 2 Rules to Snort 3](#) for additional support and information.


What to do next


Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).

Convert Snort 2 Custom Rules of a Single Intrusion Policy to Snort 3

Step 1 Choose **Policies > Intrusion**.

Step 2 In the **Intrusion Policies** tab, click **Show Snort 3 Sync status**.

Step 3 Click the **Sync** icon  of the intrusion policy.

Note If the Snort 2 and the Snort 3 versions of the intrusion policy are synchronized, then the **Sync** icon is in green . It indicates that there are no custom rules to be converted.

Step 4 Read through the summary and click the **Custom Rules** tab.

Step 5 Choose:

- **Import converted rules to this policy**—To convert the Snort 2 custom rules in the intrusion policy to Snort 3 and import them into management center as Snort 3 custom rules.
- **Download converted rules**—To convert the Snort 2 custom rules in the intrusion policy to Snort 3 and download them into your local system. You can review the converted rules in the downloaded file and later upload the file by clicking the upload icon.

Step 6 Click **Re-Sync**.

What to do next

Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).

View Snort 2 and Snort 3 Base Policy Mapping

Step 1 Choose **Policies > Intrusion**.

Step 2 Ensure the **Intrusion Policies** tab is selected.

Step 3 Click **IPS Mapping**.

Step 4 In the **IPS Policy Mapping** dialog box, click **View Mappings** to view the Snort 3 to Snort 2 intrusion policy mapping.

Step 5 Click **OK**.

Synchronize Snort 2 Rules with Snort 3

To ensure that the Snort 2 version settings and custom rules are retained and carried over to Snort 3, the management center provides the synchronization functionality. Synchronization helps Snort 2 rule override settings and custom rules, which you may have altered and added over the last few months or years, to be replicated on the Snort 3 version. This utility helps to synchronize Snort 2 version policy configuration with Snort 3 version to start with similar coverage.

If the management center is upgraded from 6.7 or earlier to 7.0 or later version, the system synchronizes the configuration. If the management center is a fresh 7.0 or later version, you can upgrade to a higher version, and the system will not synchronize any content during upgrade.

Before upgrading a device to Snort 3, if changes are made in Snort 2 version, you can use this utility to have the latest synchronization from Snort 2 version to Snort 3 version so that you start with a similar coverage.



Note On moving to Snort 3, it is recommended that you manage the Snort 3 version of the policy independently and do not use this utility as a regular operation.



Important


- Only the Snort 2 rule overrides and custom rules are copied to Snort 3 and not the other way around. You may not find a one-to-one mapping of all the intrusion rules in Snort 2 and Snort 3. Your changes to rule actions for rules that exist in both versions are synchronized when you perform the following procedure.
 - Synchronization *does not* migrate the threshold and suppression settings of any custom or system-provided rules from Snort 2 to Snort 3.
-


Step 1 Choose **Policies > Intrusion**.

Step 2 Ensure the **Intrusion Policies** tab is selected.

Step 3 Click **Show Snort 3 Sync status**.

Step 4 Identify the intrusion policy that is out-of-sync.

Step 5 Click the **Sync** icon .

Note If the Snort 2 and the Snort 3 versions of the intrusion policy are synchronized, then the **Sync** icon is in green .

Step 6 Read through the summary and download a copy of the summary if required.

Step 7 Click **Re-Sync**.

- Note**
- The synchronized settings will be applicable on the Snort 3 intrusion engine only if it is applied on a device, and after a successful deployment.
 - Snort 2 custom rules can be converted to Snort 3 using the system-provided tool. If you have any Snort 2 custom rules click the Custom Rules tab and follow the on-screen instructions to convert the rules. For more information, see [Convert Snort 2 Custom Rules of a Single Intrusion Policy to Snort 3, on page 21](#).

What to do next

Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).

Deploy Configuration Changes

After you change configurations, deploy them to the affected devices.



Note This topic covers the basic steps involved in deploying configuration changes. We *strongly* recommend that you refer the *Deploy Configuration Changes* topic in the latest version of the *Cisco Secure Firewall Management Center Configuration Guide* to understand the prerequisites and implications of deploying the changes before proceeding with the steps.



Caution When you deploy, resource demands may result in a small number of packets dropping without inspection. Additionally, deploying some configurations restarts the Snort process, which interrupts traffic inspection. Whether traffic drops during this interruption or passes without further inspection depends on how the target device handles traffic.

Step 1 On the Secure Firewall Management Center menu bar, click **Deploy** and choose **Deployment**.

The GUI page lists the devices with out-of-date configurations having **Pending** status.

- The **Modified By** column lists the users who have modified the policies or objects. Expand the device listing to view the users who have modified the policies for each policy listing.

Note Usernames are not provided for deleted policies and objects.


- The **Inspect Interruption** column indicates if traffic inspection interruption might occur in the device during deployment.


If this column is blank for a device, it indicates that there will be no traffic inspection interruptions on that device during deployment.


- The **Last Modified Time** column specifies the last time you made configuration changes.
- The **Preview** column allows you to preview the changes for the next deployment.

- The **Status** column provides the status for each deployment.

Step 2 Identify and choose the devices on which you want to deploy configuration changes.

- Search—Search for the device name, type, domain, group, or status in the search box.
- Expand—Click **Expand Arrow** () to view device-specific configuration changes to be deployed.

When you check a check box adjacent to a device, all the changes made to the device and listed under the device, are pushed for deployment. However, you can use **Policy selection** () to select individual policies or specific configurations to deploy while withholding the remaining changes without deploying them.

- Note**
- When the status in the **Inspect Interruption** column indicates (**Yes**) that deploying will interrupt inspection, and perhaps traffic, on a threat defense device, the expanded list indicates the specific configurations causing the interruption with the **Inspect Interruption** ().
 - When there are changes to interface groups, security zones, or objects, the impacted devices are shown as out-of-date on the management center. To ensure that these changes take effect, the policies with these interface groups, security zones, or objects, also need to be deployed along with these changes. The impacted policies are shown as out-of-date on the **Preview** page on the management center.

Step 3 Click **Deploy**.

Step 4 If the system identifies errors or warnings in the changes to be deployed, it displays them in the **Validation Messages** window. To view complete details, click the arrow icon before the warnings or errors.

You have the following choices:

- Deploy—Continue deploying without resolving warning conditions. You cannot proceed if the system identifies errors.
- Close—Exit without deploying. Resolve the error and warning conditions, and attempt to deploy the configuration again.

What to do next

During deployment, if there is a deployment failure, there is a possibility that the failure may impact traffic. However, it depends on certain conditions. If there are specific configuration changes in the deployment, the deployment failure may lead to traffic being interrupted. For details, see the Deploy Configuration Changes topic in the latest version of the *Cisco Secure Firewall Management Center Configuration Guide*.



PART I

Intrusion Detection and Prevention in Snort 3

- [Get Started with Snort 3 Intrusion Policies, on page 27](#)
- [Tune Intrusion Policies Using Rules, on page 37](#)
- [Tailor Intrusion Protection for Your Network Assets, on page 55](#)



CHAPTER 3

Get Started with Snort 3 Intrusion Policies

This chapter provides information on managing Snort 3 intrusion policies and access control rule configurations for intrusion detection and prevention.

- [Overview of Intrusion Policies, on page 27](#)
- [Prerequisites for Network Analysis and Intrusion Policies, on page 28](#)
- [Create a Custom Snort 3 Intrusion Policy , on page 28](#)
- [Edit Snort 3 Intrusion Policies, on page 29](#)
- [Change the Base Policy of an Intrusion Policy, on page 33](#)
- [Manage Intrusion Policies, on page 34](#)
- [Access Control Rule Configuration to Perform Intrusion Prevention, on page 35](#)

Overview of Intrusion Policies

Intrusion policies are defined sets of intrusion detection and prevention configurations that inspect traffic for security violations and, in inline deployments, can block or alter malicious traffic. Intrusion policies are invoked by your access control policy and are the system's last line of defense before traffic is allowed to its destination.

At the heart of each intrusion policy are the intrusion rules. An enabled rule causes the system to generate intrusion events for (and optionally block) traffic matching the rule. Disabling a rule stops processing of the rule.

The system delivers several base intrusion policies, which enable you to take advantage of the experience of the Cisco Talos Intelligence Group (Talos). For these policies, Talos sets intrusion and inspector rule states (enabled or disabled), as well as provides the initial configurations for other advanced settings.



Tip System-provided intrusion and network analysis policies are similarly named but contain different configurations. For example, the Balanced Security and Connectivity network analysis policy and the Balanced Security and Connectivity intrusion policy work together and can both be updated in intrusion rule updates. However, the network analysis policy governs mostly preprocessing options, whereas the intrusion policy governs mostly intrusion rules.

If you create a custom intrusion policy, you can:

- Tune detection by enabling and disabling rules, as well as by writing and adding your own rules.

- Use Secure Firewall recommendations to associate the operating systems, servers, and client application protocols detected on your network with rules specifically written to protect those assets.

An intrusion policy can drop matching packets and generate intrusion events. To configure an intrusion or preprocessor drop rule, set its state to Block.

When tailoring your intrusion policy, especially when enabling and adding rules, keep in mind that some intrusion rules require that traffic first be decoded or preprocessed in a certain way. Before an intrusion policy examines a packet, the packet is preprocessed according to configurations in a network analysis policy. If you disable a required inspector, the system automatically uses it with its current settings, although the inspector remains disabled in the network analysis policy web interface.



Caution Because preprocessing and intrusion inspection are so closely related, the network analysis and intrusion policies examining a single packet **must** complement each other. Tailoring preprocessing, especially using multiple custom network analysis policies, is an **advanced** task.

After you configure a custom intrusion policy, you can use it as part of your access control configuration by associating the intrusion policy with one or more access control rules or an access control policy's default action. This forces the system to use the intrusion policy to examine certain allowed traffic before the traffic passes to its final destination. A variable set that you pair with the intrusion policy allows you to accurately reflect your home and external networks and, as appropriate, the servers on your network.

Note that by default, the system disables intrusion inspection of encrypted payloads. This helps reduce false positives and improve performance when an encrypted connection matches an access control rule that has intrusion inspection configured.

Refer to the video for additional support and information - [Snort 3 Intrusion Policy Overview](#).

Prerequisites for Network Analysis and Intrusion Policies

To allow the Snort inspection engine to process traffic for intrusion and malware analysis, you must have the IPS license enabled for the Threat Defense device.

You must be an Admin user to manage network analysis, intrusion policies, and perform migration tasks.

Create a Custom Snort 3 Intrusion Policy

-
- Step 1** Choose **Policies > Intrusion**.
 - Step 2** Click **Create Policy**.
 - Step 3** Enter a unique **Name** and, optionally, a **Description**.
 - Step 4** Choose the **Inspection Mode**.

The selected action determines whether intrusion rules block and alert (**Prevention** mode) or only alert (**Detection** mode).

Note Before selecting the prevention mode, you might want block rules to alert only so you can identify rules that cause a lot of false positives.

- Step 5** Choose the **Base Policy**.
You can use either a system-provided policy or an existing policy as your base policy.
- Step 6** Click **Save**.
The new policy has the same settings as its base policy.

What to do next

To customize the policy, see [Edit Snort 3 Intrusion Policies, on page 29](#).

Edit Snort 3 Intrusion Policies

While editing a Snort 3 policy, all the changes are saved instantaneously. No additional action is required to save the changes.

-
- Step 1** Choose **Policies > Intrusion**.
- Step 2** Ensure the **Intrusion Policies** tab is selected.
- Step 3** Click **Snort 3 Version** next to the intrusion policy you want to configure.
- Step 4** Edit your policy:

- Change the mode—Click the **Mode** drop-down to change the inspection mode.

Caution The inspection mode is changed only for the Snort 3 version of the policy. The existing inspection mode is retained in the Snort 2 version as is, which means that your Snort 2 and Snort 3 versions of the policy will have different inspection modes. We recommend you to use this option with caution.

- **Prevention**—Triggered Block rules create an event (alert) and drop the connection.
- **Detection**—Triggered Block rules create an alert.



You can choose the detection mode before going for prevention. For example, before choosing the prevention mode, you might want block rules to alert only, so that you can identify rules that cause a lot of false positives.

- Step 5** Click the **Base Policy** layer that defines the intrusion policy's default settings.
- Search rules—Use the search field to filter the display. You can enter the GID, SID, rule message, or reference info. For example, GID:1; SID:9621—to display only rule 1:962, SID:9621,9622,9623—to display multiple rules with different SIDs. You can also click inside the Search text box to choose any of the following options:
 - apply the filters **Action = Alert**, or **Action: Block**
 - apply the **Disabled Rules** filter
 - show **Custom/User Defined Rules**
 - filter by GID, SID, or GID:SID
 - filter by CVE
 - filter by comment

- View filtered rules—Click any of the **Presets** to view rules that are set to alert, block, disabled, and so on.

Overridden rules indicate the rules where the rule action has been changed from the default action to a different action. Note that, once changed, the rule action status is Overridden even if you change it back to its original default action. However, if you select **Revert to default** from the **Rule Action** drop-down list, the Overridden status is removed.

Advanced Filters provides filter options based on the Lightweight Security Package (LSP) releases, Classifications of intrusions, and Microsoft Vulnerabilities.

- View rule documentation—Click the rule ID or the **Rule Documentation** icon to display Talos documentation for the rule.
- View a rule details—Click the **Expand Arrow** () icon in a rule row to view the rule details.
- Add rule comments—Click **Comment** () under the Comments column to add comments for a rule.

Step 6

Group Overrides—Click the **Group Overrides** layer that lists all the categories of rule groups. The top level parent rule groups with Description, Overrides and Enabled Groups, and so on is displayed. Parent rule groups cannot be updated and are read-only. Only the leaf rule groups can be updated. In each rule group, you can traverse up to the last leaf group. Across each group, you can override, include, and exclude rule groups. In the leaf rule groups, you can:

- Search rule groups—Use the search field to enter keywords and search for rule groups.
- In the left panel, you can choose any of the preset filter options to search for rule groups:
 - All—For displaying all rule groups.
 - Excluded—For excluded groups.
 - Included—For included groups.
 - Overridden—For rule group configuration that is overridden.
- Set the security level for a rule group—Navigate to the required rule group on the left pane and click it. Click **Edit** next to the **Security Level** of the rule group to increase or decrease the security level based on system-defined rule settings.

In the **Edit Security Level** dialog box, you have the option to click **Revert to Default**, which reverts the changes you made.

The management center automatically changes the action for the rules of the rule group for the configured security level. In the **Rule Overrides** layer, notice the count of Block Rules and Disabled Rules in the **Presets** every time you change the security level.

- You can make bulk changes to the security level to change the security level of all rule groups within a particular rule category. Bulk security level applies to rule groups that have more than one rule group. After a bulk update of rule groups, you can still update the security level of any of the associated rule groups within it.

There can be **mixed** security levels within rule groups; **mixed** indicates that the child groups contain a mix of security levels within the parent rule group.

- Include or exclude rule groups—The rule groups displayed are the default rule groups associated with the system-provided base intrusion policy. You can include and exclude rule groups from the intrusion policy. An excluded rule group is removed from the intrusion policy and its rules are not applied on the traffic. For information on uploading custom rules in management center, see [Add Custom Rules to Rule Groups, on page 50](#).

To exclude a rule group:

- a. Navigate the Rule Groups pane and choose the rule group that you want to exclude.
- b. Click the **Exclude** hyperlink on the right-pane.
- c. Click **Exclude**.

To include a new rule group or multiple rule groups with the uploaded custom rules or a previously excluded rule group:

- a. Click **Add** (+) next to the rule group filter dropdown list.
 - b. Choose all the rule groups you want to add by checking the check box next to it.
 - c. Click **Save**.
- For a leaf rule group, click the icon under the **Override** column header to see the rule action trail, which describes the sequence of overridden rule actions that can be assigned due to the base policy and group overrides for an intrusion rule. Rule actions can be obtained from either the base policy configurations or the user group override. The user group override takes the priority between the two; priority refers to the final overridden action that is assigned to the rule group.
 - Click the rule count (number) under the **Rule Count** column header to see a summary of rules that are part of the rule group.

Step 7 Recommendations—Click the **Recommendations** layer if you want to generate and apply Cisco recommended rules. Recommendations use the host database to enable or disable rules, based on known vulnerabilities.

Step 8 Rule Overrides—Click the **Rule Overrides** layer to choose any of the presets to view rules, which are set to alert, block, disabled, overridden, rewrite, pass, drop, or reject.

- The **Set By** column shows the default set by state (Base Policy) or modified rule state by Group Overrides, Rule Overrides, or Recommendations. The **Set By** column in **All Rules** (in the left pane) shows the trail of rule action override actions based on priority order. The priority order of rule actions is Rule Override > Recommendations > Group Override > Base Policy.
- Modify **Rule Action**—To modify rule actions, choose either of the following:
 - Bulk edit—Choose one or more rules, then choose the required action from the **Rule Action** drop-down list; and click **Save**.

Note Bulk rule action changes are supported only for the first 500 rules.
 - Single rule edit—Choose the action for the rule from the drop-down list in the **Rule Action** column.

Rule actions are:

- **Block**—Generates event, blocks current matching packet and all the subsequent packets in this connection.
- **Alert**—Generates only events for matching packet and does not drop packet or connection.
- **Disable**—Does not match traffic against this rule. No events are generated.
- **Revert to default**—Reverts to the system default action.
- **Pass**—No events are generated, allows packet to pass without further evaluation by any subsequent Snort rules.

Note The Pass action is available only for custom rules and not for system-provided rules.

- **Drop**— Generates event, drops matching packet and does not block further traffic in this connection.
- **Reject**— Generates event, drops matching packet, blocks further traffic in this connection and sends TCP reset if it is a TCP protocol to source and destination hosts.

Behavior of reject in different firewall modes and IP address or source or destination in relation to Client or Server: Snort sends RST packets to both client and server in cases of routed, inline, and bridged interfaces. Snort sends two RST packets. RST packet in clients directions will have source set to server's IP and destination set to client's IP. RST packet in servers direction will have source set to client's IP and destination set to server's IP.

- **Rewrite**— Generates event and overwrites packet contents based on the replace option in the rule.

For IPS rule action logging, see [Rule Action Logging, on page 33](#).

If there is a **React** rule, it is converted to an alert action.

Step 9 Click the **Summary** layer for a holistic view of the current changes to the policy. The policy summary page contains the following information:

- Rule distribution of the policy, that is, active rules, disabled rules, and so on.
- Option to export policy and generate report of the intrusion policy.
- Base policy details.
- Option to generate recommendations.
- Group overrides that shows the list of groups that you have overridden.
- Rule overrides that shows the list of rules that you have overridden.
- In the **Summary** layer, click the ? icon to open a popup window of the Snort helper guide that explains the Snort layering concepts.

To change the base policy, see [Change the Base Policy of an Intrusion Policy, on page 33](#).

Note You can navigate to **Objects > Intrusion Rules** and click the **Snort 3 All Rules** tab and traverse through all the intrusion rule groups. The parent rule group lists the associated child groups and rule count.

What to do next

Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).

Rule Group Reporting

The rule groups are reflected in the intrusion events generated and MITRE tactics and techniques are also called out. There are columns for MITRE tactics and techniques and for non-MITRE rule groups for intrusion events. To access the intrusion events, in management center, go to **Analysis > Intrusions > Events**, and click the **Table View of Events** tab. You can also view the intrusion event fields in the **Unified Events** viewer. In the **Analysis** tab, click **Unified Events**.

In the **Intrusion Events** page, the following fields are added for rule group reporting. Note that you must explicitly enable the mentioned columns.

- MITRE ATT&CK
- Rule Group

For information about these fields, see the section *Intrusion Event Fields* in the *Cisco Secure Firewall Management Center Administration Guide*, 7.3.

Rule Action Logging

From Management Center 7.2.0 onwards, in the **Intrusion Events** page, the event in the **Inline Result** column displays the same name as the IPS action applied to the rule, so that you can see the action that was applied on the traffic matching the rule.

For the IPS actions, the following table shows the events that are displayed in the **Inline Result** column of the **Intrusion Events** page and **Action** column for **Intrusion Event Type** in the **Unified Events** page.

IPS Action for Snort 3	Inline Result - Management Center 7.1.0 and earlier	Inline Result -Management Center 7.2.0 onwards
Alert	Pass	Alert
Block	Dropped/Would Have Dropped/Partially Dropped	Block/Would Block/Partial Block
Drop	Dropped/Would have dropped	Drop/Would drop
Reject	Dropped/Would have dropped	Reject/Would reject
Rewrite	Allow	Rewrite



Important

- In case of a rule without the “Replace” option, the **Rewrite** action is displayed as **Would Rewrite**.
- The **Rewrite** action would also be displayed as **Would Rewrite** if the "Replace" option is specified, but the IPS policy is in Detection mode or the device is in Inline-TAP/Passive mode.



Note

In case of backward compatibility (Management Center 7.2.0 managing a Threat Defense 7.1.0 device), the events mentioned are applicable only to the Alert IPS action where **Pass** is displayed as **Alert** for events. For all the other actions, the events for Management Center 7.1.0 are applicable.

Change the Base Policy of an Intrusion Policy

You can choose a different system-provided or custom policy as your base policy.

You can chain up to five custom policies, with four of the five using one of the other four previously created policies as its base policy; the fifth must use a system-provided policy as its base.

-
- Step 1** Choose **Policies > Intrusion**.
- Step 2** Click **Edit** (✎) next to the intrusion policy you want to configure.
- Step 3** Choose a policy from the **Base Policy** drop-down list.
- Step 4** Click **Save**.
-

What to do next

Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).

Manage Intrusion Policies

On the Intrusion Policy page (**Policies > Intrusion**) you can view your current custom intrusion policies, along with the following information:

- Number of access control policies and devices are using the intrusion policy to inspect traffic
- In a multidomain deployment, the domain where the policy was created

In a multidomain deployment, the system displays policies created in the current domain, which you can edit. It also displays policies created in ancestor domains, which you cannot edit. To view and edit policies created in a lower domain, switch to that domain.

-
- Step 1** Choose **Policies > Intrusion**.
- Step 2** Manage your intrusion policy:
- Create — Click **Create Policy**; see [Create a Custom Snort 3 Intrusion Policy, on page 28](#).
 - Delete — Click **Delete** (■) next to the policy you want to delete. The system prompts you to confirm and informs you if another user has unsaved changes in the policy. Click **OK** to confirm.
If the controls are dimmed, the configuration belongs to an ancestor domain, or you do not have permission to modify the configuration.
 - Edit intrusion policy details — Click **Edit** (✎) next to the policy you want to edit. You can edit the **Name**, **Inspection Mode**, and the **Base Policy** of the intrusion policy.
 - Edit intrusion policy settings — Click **Snort 3 Version**; see [Edit Snort 3 Intrusion Policies, on page 29](#).
 - Export — If you want to export an intrusion policy to import on another management center, click **Export**; see the *Exporting Configurations* topic in the latest version of the *Cisco Secure Firewall Management Center Configuration Guide*.
 - Deploy — Choose **Deploy > Deployment**; see [Deploy Configuration Changes, on page 23](#).
 - Report — Click **Report**; see the *Generating Current Policy Reports* topic in the latest version of the *Cisco Secure Firewall Management Center Configuration Guide*. Generates two reports, one for each policy version.
-

Access Control Rule Configuration to Perform Intrusion Prevention

An access control policy can have multiple access control rules associated with intrusion policies. You can configure intrusion inspection for any Allow or Interactive Block access control rule, which permits you to match different intrusion inspection profiles against different types of traffic on your network before it reaches its final destination.

Whenever the system uses an intrusion policy to evaluate traffic, it uses an associated *variable set*. Variables in a set represent values commonly used in intrusion rules to identify source and destination IP addresses and ports. You can also use variables in intrusion policies to represent IP addresses in rule suppressions and dynamic rule states.



Tip Even if you use system-provided intrusion policies, Cisco **strongly** recommends you configure the system's intrusion variables to accurately reflect your network environment. At a minimum, modify default variables in the default set.

Understanding System-Provided and Custom Intrusion Policies

Cisco delivers several intrusion policies with the system. By using system-provided intrusion policies, you can take advantage of the experience of the Cisco Talos Intelligence Group (Talos). For these policies, Talos sets intrusion and preprocessor rule states, as well as provides the initial configurations for advanced settings. You can use system-provided policies as-is, or you can use them as the base for custom policies. Building custom policies can improve the performance of the system in your environment and provide a focused view of the malicious traffic and policy violations occurring on your network.

Connection and Intrusion Event Logging

When an intrusion policy invoked by an access control rule detects an intrusion and generates an intrusion event, it saves that event to the Management Center. The system also automatically logs the end of the connection where the intrusion occurred to the Management Center database, regardless of the logging configuration of the access control rule.

Access Control Rule Configuration and Intrusion Policies

The number of unique intrusion policies you can use in a single access control policy depends on the model of the target devices; more powerful devices can handle more. Every unique **pair** of intrusion policy and variable set counts as one policy. Although you can associate a different intrusion policy-variable set pair with each Allow and Interactive Block rule (as well as with the default action), you cannot deploy an access control policy if the target devices have insufficient resources to perform inspection as configured.

Configure an Access Control Rule to Perform Intrusion Prevention

You must be an Admin, Access Admin, or Network Admin to perform this task.

-
- Step 1** In the access control policy editor, create a new rule or edit an existing rule; see the *Access Control Rule Components* topic in the latest version of the *Cisco Secure Firewall Management Center Configuration Guide*.
- Step 2** Ensure the rule action is set to **Allow**, **Interactive Block**, or **Interactive Block with reset**.
- Step 3** Click **Inspection**.
- Step 4** Choose a system-provided or a custom intrusion policy, or choose **None** to disable intrusion inspection for traffic that matches the access control rule.
- Step 5** If you want to change the variable set associated with the intrusion policy, choose a value from the **Variable Set** drop-down list.
- Step 6** Click **Save** to save the rule.
- Step 7** Click **Save** to save the policy.
-

What to do next

Deploy configuration changes; see [Deploy Configuration Changes](#), on page 23.



CHAPTER 4

Tune Intrusion Policies Using Rules

This chapter provides information on custom rules in Snort 3, intrusion rule action, intrusion event notification filters in an intrusion policy, converting Snort 2 custom rules to Snort 3, and adding rule groups with custom rules to an intrusion policy.

- [Overview of Tuning Intrusion Rules, on page 37](#)
- [Intrusion Rule Types, on page 38](#)
- [Prerequisites for Network Analysis and Intrusion Policies, on page 39](#)
- [Custom Rules in Snort 3, on page 39](#)
- [View Snort 3 Intrusion Rules in an Intrusion Policy, on page 42](#)
- [Intrusion Rule Action, on page 42](#)
- [Intrusion Event Notification Filters in an Intrusion Policy, on page 43](#)
- [Add Intrusion Rule Comments, on page 48](#)
- [Snort 2 Custom Rules Conversion to Snort 3, on page 48](#)
- [Add Custom Rules to Rule Groups, on page 50](#)
- [Add Rule Groups with Custom Rules to an Intrusion Policy, on page 51](#)
- [Manage Custom Rules in Snort 3, on page 51](#)
- [Delete Custom Rules, on page 52](#)
- [Delete Rule Groups, on page 53](#)

Overview of Tuning Intrusion Rules

You can configure rule states and other settings for shared object rules, standard text rules, and inspector rules.

You enable a rule by setting its rule state to Alert or to Block. Enabling a rule causes the system to generate events on traffic matching the rule. Disabling a rule stops processing of the rule. You can also set your intrusion policy so that a rule set to Block generates events on, and drops, matching traffic.

You can filter rules to display a subset of rules, enabling you to select the exact set of rules where you want to change rule states or rule settings.

When an intrusion rule or rule argument requires a disabled inspector, the system automatically uses it with its current configuration even though it remains disabled in the network analysis policy's web interface.

Intrusion Rule Types

An intrusion rule is a specified set of keywords and arguments that the system uses to detect attempts to exploit vulnerabilities in your network. As the system analyzes network traffic, it compares packets against the conditions specified in each rule, and triggers the rule if the data packet meets all the conditions specified in the rule.

An intrusion policy contains:

- *intrusion rules*, which are subdivided into *shared object rules* and *standard text rules*
- *inspector rules*, which are associated with a detection option of the packet decoder or with one of the inspectors included with the system

The following table summarizes attributes of these rule types:

Table 2: Intrusion Rule Types

Type	Generator ID (GID)	Snort ID (SID)	Source	Can Copy?	Can Edit?
shared object rule	3	lower than 1000000	Cisco Talos Intelligence Group (Talos)	yes	limited
standard text rule	1 (Global domain or legacy GID)	lower than 1000000	Talos	yes	limited
	1000 - 2000 (descendant domain)	1000000 or higher	Created or imported by user	yes	yes
preprocessor rule	decoder- or preprocessor-specific	lower than 1000000	Talos	no	no
		1000000 or higher	Generated by the system during option configuration	no	no

You cannot save changes to any rule created by Talos, but you can save a copy of a modified rule as a custom rule. You can modify either variables used in the rule or rule header information (such as source and destination ports and IP addresses). In a multidomain deployment, rules created by Talos belong to the Global domain. Administrators in descendant domains can save local copies of the rules, which they can then edit.

For the rules it creates, Talos assigns default rule states in each default intrusion policy. Most preprocessor rules are disabled by default and must be enabled if you want the system to generate events for preprocessor rules and, in an inline deployment, drop offending packets.

Prerequisites for Network Analysis and Intrusion Policies

To allow the Snort inspection engine to process traffic for intrusion and malware analysis, you must have the IPS license enabled for the Threat Defense device.

You must be an Admin user to manage network analysis, intrusion policies, and perform migration tasks.

Custom Rules in Snort 3

You can create a custom intrusion rule by importing a local rule file. The rule file can either have a `.txt` or `.rules` extension. The system saves the custom rule in the local rule category, regardless of the method you used to create it. A custom rule must belong to a rule group. However, a custom rule can be a part of two or more groups as well.

When you create a custom intrusion rule, the system assigns it a unique rule number, which has the format `GID:SID:Rev`. The elements of this number are:

- **GID**—Generator ID. For custom rules, it is not necessary to specify the GID. The system automatically generates the GID based on whether you are in the Global domain or a sub-domain while uploading the rules. For all standard text rules, this value is 2000 for a Global domain.
- **SID**—Snort ID. Indicates whether the rule is a local rule or a system rule. When you create a new rule, assign a unique SID to the rule.
SID numbers for local rules start at 1000000, and the SID for each new local rule is incremented by one.
- **Rev**—The revision number. For a new rule, the revision number is one. Each time you modify a custom rule the revision number should be incremented by one.

In a custom standard text rule, you set the rule header settings and the rule keywords and arguments. You can use the rule header settings to focus the rule to only match traffic using a specific protocol and traveling to or from specific IP addresses or ports.



Note Snort 3 custom rules cannot be edited. Ensure custom rules have a valid classification message for `classtype` within the rule text. If you import a rule without a classification or wrong classification, then delete and recreate the rule.

Sensitive Data Detection in Snort 3

Sensitive data such as social security numbers, credit card numbers, emails, and so on may be leaked onto the internet, intentionally or accidentally. Sensitive data detection is used to detect and generate events on possible sensitive data leakage. Events are generated only if there is a transfer of significant amount of Personally Identifiable Information (PII) data. Sensitive data detection can mask PII in the output of events.

sd_pattern Option

Use the `sd_pattern` IPS option to detect and filter PII. This information includes credit card numbers, U.S. Social Security numbers, phone numbers, and email addresses. A regular expression (regex) syntax is available for defining your own PII.

The `sd_pattern` option has the following settings:

- **Pattern**—An implicit, required setting that specifies the regular expression to look for in the PDU. The regex must be written in PCRE syntax.
- **Threshold**—An explicit, optional setting that specifies the number of matches in the PDU required to generate an event.

The `sd_pattern` as IPS rule option is available in Snort with no requirements for additional inspectors. The rule option's syntax is:

```
sd_pattern: "<pattern>"[, threshold <count>];
```

For example:

```
sd_pattern:"credit_card", threshold 2;
```

Built-in Patterns

There are five built-in patterns for sensitive data. To use the built-in patterns in the "pattern" setting, you must specify the name of the PII type that needs to be matched and the necessary regex is substituted for it. The PII name and regex mappings or patterns are described as follows:

- **credit_card**—

```
\d{4}\d?\d{4}\D?\d{2}\D?\d{2}\D?\d{3,4}
```

- **us_social**—

```
[0-8]\d{2}-\d{2}-\d{4}
```

- **us_social_nodashes**—

```
[0-8]\d{8}
```

- **Email**—

```
[a-zA-Z0-9!#$%&'*/\=?^_`{|}~-]+(?:\.[a-zA-Z0-9!#$%&'*/\=?^_`{|}~-]+)*@(?:[a-zA-Z0-9](?:[a-zA-Z0-9-]*[a-zA-Z0-9])?\.)+[a-zA-Z0-9](?:[a-zA-Z0-9-]*[a-zA-Z0-9])?
```

- **us_phone**—

```
(?:\+?1[-.\s]?)?(?([2-9][0-8]\d)\)?[-.\s]([2-9]\d{2})[-.\s](\d{4})
```

PII Name	Pattern
credit_card	\d{4}\d?\d{4}\D?\d{2}\D?\d{2}\D?\d{3,4}
us_social	[0-8]\d{2}-\d{2}-\d{4}
us_social_nodashes	[0-8]\d{8}
Email	[a-zA-Z0-9!#\$%&'*/\=?^_`{ }~-]+(?:\.[a-zA-Z0-9!#\$%&'*/\=?^_`{ }~-]+)*@(?:[a-zA-Z0-9](?:[a-zA-Z0-9-]*[a-zA-Z0-9])?\.)+[a-zA-Z0-9](?:[a-zA-Z0-9-]*[a-zA-Z0-9])?
us_phone	(?:\+?1[-.\s]?)?(?([2-9][0-8]\d)\)?[-.\s]([2-9]\d{2})[-.\s](\d{4})

Masking for data matching these patterns only work with system-provided rules or built-in patterns for Credit Cards, U.S. Social Security numbers, emails, and U.S. phone numbers. Masking does not work for custom rules or user-defined PII patterns. Rules are available in the Lightweight Security Package (LSP) for sensitive data, gid:13. By default, they are not enabled in any system-provided policy.

The sensitive data rules in LSP cover all built-in patterns and have the following threshold values:

- credit_card: 2
- us_social: 2
- us_social_nodashes: 20
- email: 20
- us_phone: 20

You can use the `sd_pattern` option to create custom rules and modify existing rules. To do this, use the Snort 3 intrusion policy interface.

An example of a rule with `sd_pattern` with a custom pattern and threshold:

```
alert tcp (sid: 100000001; sd_pattern:"[\\w-\\.]+@[\\w-]+\\.]+[\\w-]{2,4}",threshold 4; msg: "email, threshold 4")
```

Examples

An example of custom rules using sensitive data detection:

Rule with built-in pattern:

```
alert tcp (
  msg:"SENSITIVE-DATA Email";
  flow:only_stream;
  pkt_data;
  sd_pattern:"email", threshold 5;
  service:http, smtp, ftp-data, imap, pop3;
  gid:2000;
  sid:1000001;
)
```

Rule with custom pattern

```
alert tcp (
  msg:"SENSITIVE-DATA US phone numbers";
  flow:only_stream;
  file_data;
  sd_pattern:"+?3?8?(0[\\s\\. -]\\d{2}[\\s\\. -]\\d{3}[\\s\\. -]\\d{2}[\\s\\. -]\\d{2})", threshold 2;
  service:http, smtp, ftp-data, imap, pop3;
  gid:2000;
  sid:1000002;
)
```

Here are some more examples of complete Snort IPS rules with built-in sensitive data patterns:

- alert tcp (sid:1; msg:"Credit Card"; sd_pattern:"credit_card", threshold 2;)
- alert tcp (sid:2; msg:"US Social Number"; sd_pattern:"us_social", threshold 2;)
- alert tcp (sid:3; msg:"US Social Number No Dashes"; sd_pattern:"us_social_nodashes", threshold 2;)
- alert tcp (sid:4; msg:"US Phone Number"; sd_pattern:"us_phone", threshold 2;)
- alert tcp (sid:5; msg:"Email"; sd_pattern:"email", threshold 2;)

Disabling data masking is not supported in the Secure Firewall Management Center and Secure Firewall Device Manager.

View Snort 3 Intrusion Rules in an Intrusion Policy

You can adjust how rules are displayed in the intrusion policy. You can also display the details for a specific rule to see rule settings, rule documentation, and other rule specifics.

-
- Step 1** Choose **Policies > Intrusion**.
- Step 2** Click **Snort 3 Version** next to the policy.
- Step 3** While viewing the rules, you can:

- Filter the rules.
- Choose a rule group to see rules related to that group.
- View an intrusion rule's details.
- View rule comments.
- View rule documentation.

See [Edit Snort 3 Intrusion Policies, on page 29](#) for details on performing these tasks.

Intrusion Rule Action

Intrusion rule action allows you to enable or disable the rule within an individual intrusion policy, as well as specify which action the system takes if monitored conditions trigger the rule.

The Cisco Talos Intelligence Group (Talos) sets the default action of each intrusion and inspector rule in each default policy. For example, a rule may be enabled in the Security over Connectivity default policy and disabled in the Connectivity over Security default policy. Talos sometimes uses a rule update to change the default action of one or more rules in a default policy. If you allow rule updates to update your base policy, you also allow the rule update to change the default action of a rule in your policy when the default action changes in the default policy you used to create your policy (or in the default policy it is based on). Note, however, that if you have changed the rule action, the rule update does not override your change.

When you create an intrusion rule, it inherits the default actions of the rules in the default policy you use to create your policy.

Intrusion Rule Action Options

In an intrusion policy, you can set a rule's action to the following values:

Alert

You want the system to detect a specific intrusion attempt and generate an intrusion event when it finds matching traffic. When a malicious packet crosses your network and triggers the rule, the packet is sent to its destination and the system generates an intrusion event. The malicious packet reaches its target, but you are notified through the event logging.

Block

You want the system to detect a specific intrusion attempt, drop the packet containing the attack, and generate an intrusion event when it finds matching traffic. The malicious packet never reaches its target, and you are notified through the event logging.

Disable

You do not want the system to evaluate matching traffic.



Note Choosing either the **Alert** or **Block** options enables the rule. Choosing **Disable** disables the rule.

We **strongly** recommend that you **do not** enable all the intrusion rules in an intrusion policy. The performance of your managed device is likely to degrade if all rules are enabled. Instead, tune your rule set to match your network environment as closely as possible.

Set Intrusion Rule Action

Intrusion rule actions are policy-specific.

Step 1 Choose **Policies > Intrusion**.

Step 2 Click **Snort 3 Version** next to the policy you want to edit.

Tip This page shows the total number of:

- disabled rules
- enabled rules set to Alert
- enabled rules set to Block
- overridden rules

Step 3 Choose the rule or rules where you want to set the rule action.

Step 4 Choose one of the rule actions from the **Rule Action** drop-down list. See [Edit Snort 3 Intrusion Policies, on page 29](#) for more information about the different rule actions.

Step 5 Click **Save**.

What to do next

Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).

Intrusion Event Notification Filters in an Intrusion Policy

The importance of an intrusion event can be based on frequency of occurrence, or on source or destination IP address. In some cases you may not care about an event until it has occurred a certain number of times. For example, you may not be concerned if someone attempts to log into a server until they fail a certain number

of times. In other cases, you may only need to see a few occurrences to know there is a widespread problem. For example, if a DoS attack is launched against your web server, you may only need to see a few occurrences of an intrusion event to know that you need to address the situation. Seeing hundreds of the same event only overwhelms your system.

Intrusion Event Thresholds

You can set thresholds for individual rules to limit the number of times the system logs and displays an intrusion event based on how many times the event is generated within a specified time period. This can prevent you from being overwhelmed with a large number of identical events. You can set thresholds per shared object rule, standard text rule, or inspector rule.

Set Intrusion Event Thresholds

To set a threshold, first specify the thresholding type.

Table 3: Thresholding Options

Option	Description
Limit	Logs and displays events for the specified number of packets (specified by the Count argument) that trigger the rule during the specified time period. For example, if you set the type to Limit , the Count to 10, and the Seconds to 60, and 14 packets trigger the rule, the system stops logging events for the rule after displaying the first 10 that occur within the same minute.
Threshold	Logs and displays a single event when the specified number of packets (specified by the Count argument) trigger the rule during the specified time period. Note that the counter for the time restarts after you hit the threshold count of events and the system logs that event. For example, you set the type to Threshold , Count to 10, and Seconds to 60, and the rule triggers 10 times by second 33. The system generates one event, then resets the Seconds and Count counters to 0. The rule then triggers another 10 times in the next 25 seconds. Because the counters reset to 0 at second 33, the system logs another event.
Both	Logs and displays an event once per specified time period, after the specified number (count) of packets trigger the rule. For example, if you set the type to Both , Count to two, and Seconds to 10, the following event counts result: <ul style="list-style-type: none"> • If the rule is triggered once in 10 seconds, the system does not generate any events (the threshold is not met) • If the rule is triggered twice in 10 seconds, the system generates one event (the threshold is met when the rule triggers the second time) • If the rule is triggered four times in 10 seconds, the system generates one event (the threshold is met when the rule triggers the second time, and following events are ignored)

Secondly, specify tracking, which determines whether the event threshold is calculated per source or destination IP address.

Table 4: Thresholding IP Options

Option	Description
Source	Calculates event instance count per source IP address.
Destination	Calculates event instance count per destination IP address.

Finally, specify the number of instances and time period that define the threshold.

Table 5: Thresholding Instance/Time Options

Option	Description
Count	The number of event instances per specified time period per tracking IP address required to meet the threshold.
Seconds	The number of seconds that elapse before the count resets. If you set the threshold type to limit , the tracking to Source IP , the count to 10, and the seconds to 10, the system logs and displays the first 10 events that occur in 10 seconds from a given source port. If only 7 events occur in the first 10 seconds, the system logs and displays those; if 40 events occur in the first 10 seconds, the system logs and displays 10, then begins counting again when the 10-second time period elapses.

Note that you can use intrusion event thresholding alone or in any combination with rate-based attack prevention, the `detection_filter` keyword, and intrusion event suppression.



Tip You can also add thresholds from within the packet view of an intrusion event.

Set Threshold for an Intrusion Rule in Snort 3

You can set a single threshold for a rule from the Rule Detail page. Adding a threshold overwrites any existing threshold for the rule.

-
- Step 1** Choose **Objects > Intrusion Rules**.
 - Step 2** Click **Snort 3 All Rules** tab.
 - Step 3** From an intrusion rule's Alert Configuration column, click the **None** link.
 - Step 4** Click **Edit** (✎).
 - Step 5** In the Alert Configuration window, click the **Threshold** tab.
 - Step 6** From the **Type** drop-down list, choose the type of threshold you want to set:
 - Choose **Limit** to limit notification to the specified number of event instances per time period.
 - Choose **Threshold** to provide notification for each specified number of event instances per time period.
 - Choose **Both** to provide notification once per time period after a specified number of event instances.
 - Step 7** Choose **Source** or **Destination** in the **Track By** field to indicate whether you want the event instances tracked by source or destination IP address.

- Step 8** Enter the number of event instances you want to use as your threshold in the **Count** field.
- Step 9** Enter a number that specifies the time period, in seconds, for which event instances are tracked in the **Seconds** field.
- Step 10** Click **Save**.
- Refer to the video [Snort 3 Suppression and Threshold](#) for additional support and information.

What to do next

Deploy configuration changes; see [Deploy Configuration Changes](#).

View and Delete Intrusion Event Thresholds

To view or delete an existing threshold setting for a rule, use the Rules Details view to display the configured settings for a threshold and see if they are appropriate for your system. If they are not, you can add a new threshold to overwrite the existing values.

- Step 1** Choose **Objects > Intrusion Rules**.
- Step 2** Click **Snort 3 All Rules** tab.
- Step 3** Choose the rule with a configured threshold as shown in the **Alert Configuration** column (the **Alert Configuration** column displays **Threshold** as a link for the rule).
- Step 4** To remove the threshold for the rule, click **Threshold** link in the **Alert Configuration** column.
- Step 5** Click **Edit** (✎).
- Step 6** Click **Threshold** tab.
- Step 7** Click **Reset**.
- Step 8** Click **Save**.

What to do next

Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).

Intrusion Policy Suppression Configuration

You can suppress intrusion event notification when a specific IP address or range of IP addresses triggers a specific rule or inspector. This is useful for eliminating false positives. For example, if you have a mail server that transmits packets that look like a specific exploit, you might suppress event notification for that event when it is triggered by your mail server. The rule triggers for all packets, but you only see events for legitimate attacks.

Intrusion Policy Suppression Types

Note that you can use intrusion event suppression alone or in any combination with rate-based attack prevention, the `detection_filter` keyword, and intrusion event thresholding.



Tip You can add suppressions from within the packet view of an intrusion event. You can also access suppression settings by using the **Alert Configuration** column on the intrusion rules editor page (**Objects > Intrusion Rules > Snort 3 All Rules**).

Set Suppression for an Intrusion Rule in Snort 3

You can set one or more suppressions for a rule in your intrusion policy.

Before you begin

Ensure you create the required network objects to be added for source or destination suppression.

-
- Step 1** Choose **Objects > Intrusion Rules**.
- Step 2** Click **Snort 3 All Rules** tab.
- Step 3** Click the **None** link in the intrusion rule's Alert Configuration column.
- Step 4** Click **Edit** (✎).
- Step 5** From the **Suppressions** tab, click the add icon (+) next to any of the following options:
- Choose **Source Networks** to suppress events generated by packets originating from a specified source IP address.
 - Choose **Destination Networks** to suppress events generated by packets going to a specified destination IP address.
- Step 6** Select any of the preset networks in the **Network** drop-down list.
- Step 7** Click **Save**.
- Step 8** (Optional) Repeat the last three steps if required.
- Step 9** Click **Save** in the Alert Configuration window.

What to do next

Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).

View and Delete Suppression Conditions

You may want to view or delete an existing suppression condition. For example, you can suppress event notification for packets originating from a mail server IP address because the mail server normally transmits packets that look like exploits. If you then decommission that mail server and reassign the IP address to another host, you should delete the suppression conditions for that source IP address.

-
- Step 1** Choose **Objects > Intrusion Rules**.
- Step 2** Click **Snort 3 All Rules** tab.
- Step 3** Choose the rule for which you want to view or delete suppressions.
- Step 4** Click **Suppression** in the **Alert Configuration** column.
- Step 5** Click **Edit** (✎).

- Step 6** Click **Suppressions** tab.
- Step 7** Remove the suppression by clicking **Clear** (✕) next to the suppression.
- Step 8** Click **Save**.

What to do next

Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).

Add Intrusion Rule Comments

You can add comments to rules in your intrusion policy. Comments added this way are policy-specific; that is, comments you add to a rule in one intrusion policy are not visible in other intrusion policies.

- Step 1** Choose **Policies > Intrusion**.
- Step 2** Click **Snort 3 Version** next to the policy you want to edit.
- Step 3** In the right side of the page where all the rules are listed, choose the rule where you want to add a comment.
- Step 4** Click **Comment** (🗨) under the **Comments** column.
- Step 5** In the **Comments** field, enter the rule comment.
- Step 6** Click **Add Comment**.
- Step 7** Click **Save**.

Tip The system displays a **Comment** (🗨) next to the rule in the Comments column.

What to do next

Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).

Snort 2 Custom Rules Conversion to Snort 3

If you are using custom rules, make sure you are prepared to manage that rule set for Snort 3 prior to conversion from Snort 2 to Snort 3. If you are using a rule set from a third-party vendor, contact that vendor to confirm that their rules will successfully convert to Snort 3 or to obtain a replacement rule set written natively for Snort 3. If you have custom rules that you have written yourself, familiarize with writing Snort 3 rules prior to conversion, so you can update your rules to optimize Snort 3 detection after conversion. See the links below to learn more about writing rules in Snort 3.

- <https://blog.snort.org/2020/08/how-rules-are-improving-in-snort-3.html>
- <https://blog.snort.org/2020/10/talos-transition-to-snort-3.html>

You can refer to other blogs at <https://blog.snort.org/> to learn more about Snort 3 rules.

To use the system-provided tool to convert Snort 2 rules to Snort 3 rules, see [Snort 2 Custom Rules Conversion to Snort 3, on page 48](#).



Important Snort 2 network analysis policy (NAP) settings *cannot* be copied to Snort3 automatically. NAP settings have to be manually replicated in Snort 3.

Convert all Snort 2 Custom Rules across all Intrusion Policies to Snort 3

Step 1 Choose **Objects > Intrusion Rules** .

Step 2 Click **Snort 3 All Rules** tab.

Step 3 Ensure **All Rules** is selected in the left pane.

Step 4 Click the **Tasks** drop-down list and choose:

- **Convert Snort 2 rules and import**—To automatically convert all the Snort 2 custom rules across all the intrusion policies to Snort 3 and import them into management center as Snort 3 custom rules.
- **Convert Snort 2 rules and download**—To automatically convert all the Snort 2 custom rules across all the intrusion policies to Snort 3 and download them into your local system.

Step 5 Click **OK**.

- Note**
- If you selected **Convert and import** in the previous step, then all the converted rules are saved under a newly created rule group **All Snort 2 Converted Global** under **Local Rules**.
 - If you selected **Convert and download** in the previous step, then save the rules file locally. You can review the converted rules in the downloaded file and later upload them by following the steps in [Add Custom Rules to Rule Groups, on page 50](#).

Refer to the video [Converting Snort 2 Rules to Snort 3](#) for additional support and information.


What to do next


Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).

Convert Snort 2 Custom Rules of a Single Intrusion Policy to Snort 3

Step 1 Choose **Policies > Intrusion**.

Step 2 In the **Intrusion Policies** tab, click **Show Snort 3 Sync status**.

Step 3 Click the **Sync** icon  of the intrusion policy.

- Note**
- If the Snort 2 and the Snort 3 versions of the intrusion policy are synchronized, then the **Sync** icon is in green . It indicates that there are no custom rules to be converted.

Step 4 Read through the summary and click the **Custom Rules** tab.

Step 5 Choose:

- **Import converted rules to this policy**—To convert the Snort 2 custom rules in the intrusion policy to Snort 3 and import them into management center as Snort 3 custom rules.
- **Download converted rules**—To convert the Snort 2 custom rules in the intrusion policy to Snort 3 and download them into your local system. You can review the converted rules in the downloaded file and later upload the file by clicking the upload icon.

Step 6 Click **Re-Sync**.

What to do next

Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).

Add Custom Rules to Rule Groups

Uploading custom rules in the management center adds the custom rules that you have created locally to the list of all the Snort 3 rules.

Step 1 Choose **Objects > Intrusion Rules**.

Step 2 Click **Snort 3 All Rules** tab.

Step 3 Click the **Tasks** drop-down list.

Step 4 Click **Upload Snort 3 Rules**.

Step 5 Drag and drop the `.txt` or `.rules` file that contains the Snort 3 custom rules that you have created.

Step 6 Click **OK**.

Note If there are any errors in the selected file, then you cannot proceed further. You can download the error file and **Replace File** link to upload version 2 of the file, after fixing the errors.

Step 7 Associate rules to a rule group to add the new rules to that group.

You can also create a new custom rule group (by clicking the **Create New Custom Rule Group** link) and then add the rules to the new group.

Note If there are no existing local rule groups, then proceed by clicking **Create New Custom Rule Group to proceed**. Enter a **Name** for the new rule group and click **Save**.

Step 8 Choose either of the following:

- **Merge Rules** to merge the new rules that you are adding with the existing rules in the rule group.
- **Replace all rules in the group with file contents** to replace all the exiting rules with the new rules that you are adding.

Note If you chose more than one rule group in the previous step, then only the **Merge Rules** option is available.

Step 9 Click **Next**.

Review the summary to know the new rule IDs that are being added and optionally download it.

Step 10 Click **Finish**.



Important The rule action of all the uploaded rules is in the disabled state. You have to change them to the required state to ensure the rules are active.

What to do next

- Uploading custom rules in the management center adds the custom rules that you have created to the list of all the Snort 3 rules. To enforce these custom rules on the traffic, add and enable these rules in the required intrusion policies. For information on adding rule groups with custom rules to an intrusion policy, see [Add Rule Groups with Custom Rules to an Intrusion Policy, on page 51](#). For information on enabling custom rules, see [Manage Custom Rules in Snort 3, on page 51](#).
- Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).

Add Rule Groups with Custom Rules to an Intrusion Policy

Custom rules that are uploaded in the system have to be enabled in an intrusion policy to enforce those rules on the traffic. After uploading custom rules on management center, add the rule group with the new custom rules in the intrusion policy.

- Step 1** Choose **Policies > Intrusion**.
- Step 2** In the **Intrusion Policies** tab, click the **Snort 3 Version** of the intrusion policy.
- Step 3** Click **Add (+)** next to the Rule Groups search bar.
- Step 4** In the **Add Rule Groups** window, click the **>** icon next to a rule group to expand the local rule group.
- Step 5** Check the check box next to the uploaded custom rules group.
- Step 6** Click **Save**.

What to do next

Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).

Manage Custom Rules in Snort 3

Custom rules that are uploaded in the system have to be added to an intrusion policy and enabled to enforce those rules on the traffic. You can enable the uploaded custom rules across all policies or selectively on individual policies.

Follow the steps to enable custom rules in one or many intrusion policies:

-
- Step 1** Choose **Objects > Intrusion Rules**.
- Step 2** Click **Snort 3 All Rules** tab.
- Step 3** Expand **Local Rules**.
- Step 4** Select the required rule group.
- Step 5** Select the rules by checking the check boxes next to them.
- Step 6** Select **Per Intrusion Policy** from the **Rule Actions** drop-down list.
- Step 7** Choose:
- **All Policies**—to have the same rule actions for all the rules to be added.
 - **Per Intrusion Policy**—to have different rule actions for each intrusion policy.
- Step 8** Set the rule actions:
- If you selected All Policies in the previous step, then select the required rule action from the **Select Override state** drop-down list.
 - If you selected Per Intrusion Policy in the previous step, then select the **Rule Action** against the policy name. To add more policies, click **Add Another**.
- Step 9** Optionally, add a comment in the **Comments** text box.
- Step 10** Click **Save**.
-

What to do next

Deploy the changes on the device. See, [Deploy Configuration Changes, on page 23](#).

Delete Custom Rules

- Step 1** Choose **Objects > Intrusion Rules**.
- Step 2** Click **Snort 3 All Rules** tab.
- Step 3** Expand **Local Rules** in the left pane.
- Step 4** Check the check boxes of the rules you want to delete.
- Step 5** Ensure that the rule action for all the rules that you select is **Disable**.
- If required, follow the steps below to disable the rule action for multiple selected rules:
- a) From the **Rule Actions** drop-down box, select **Per Intrusion Policy**.
 - b) Select **All Policies** radio button.
 - c) Select **Disable** from the **Select Override state** drop-down list.
 - d) Click **Save**.
 - e) Check the check boxes of the rules you want to delete.
- Step 6** From the **Rule Actions** drop-down list, select **Delete**.

Step 7 Click **Delete** in the Delete Rules pop-up window.

What to do next

Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).

Delete Rule Groups

Before you begin

Exclude the rule group you want to delete from all intrusion policies where you have included it. For steps on excluding a rule group from an intrusion policy, see [Edit Snort 3 Intrusion Policies, on page 29](#).

Step 1 Choose **Objects > Intrusion Rules**.

Step 2 Click **Snort 3 All Rules** tab.


Step 3 Expand **Local Rules** in the left pane.

Step 4 Select the rule group to be deleted.

Step 5 Ensure the rule action for all the rules in the group is set to **Disable** before proceeding.

If the rule action for any of the rules is anything other than **Disable**, then you cannot delete the rule group. If required, follow the steps below to disable the rule action for all the rules:

- a) Check the check box below the **Rule Actions** drop-down list to select all the rules in the group.
- b) From the **Rule Actions** drop-down box, select **Per Intrusion Policy**.
- c) Select **All Policies** radio button.
- d) Select **Disable** from the **Select Override state** drop-down list.
- e) Click **Save**.

Step 6 Click the **Delete** () next to the rule group.

Step 7 Click **OK** in the Delete Rule Group pop-up window.

What to do next

Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).



CHAPTER 5

Tailor Intrusion Protection for Your Network Assets

This chapter provides an insight into Secure Firewall recommended rules and generating and applying Secure Firewall recommended rules.

- [Snort 3 Rule Changes in LSP Updates](#) , on page 55
- [Overview of Secure Firewall Recommended Rules](#), on page 55
- [Prerequisites for Network Analysis and Intrusion Policies](#), on page 56
- [Generate New Secure Firewall Recommendations in Snort 3](#), on page 57

Snort 3 Rule Changes in LSP Updates

During regular Snort 3 Lightweight Security Package (LSP) updates, an existing system-defined intrusion rule may be replaced with a new intrusion rule. There could be possibilities of a single rule being replaced with multiple rules, or multiple rules being replaced with a single rule. This occurs when better detection is possible for which rules are combined or expanded. For better management, some existing system-defined rules may also be removed as a part of the LSP update.

To get notifications for changes to any *overridden* system-defined rules during LSP updates, ensure that the **Retain user overrides for deleted Snort 3 rules** check box is checked.

To navigate to the **Retain user overrides for deleted Snort 3 rules** check box, click **Cog** (⚙️), and then choose **Configuration > Intrusion Policy Preferences**.

By default this check box is checked. When this check box is checked, the system retains the rule overrides in the new replacement rules that are added as a part of the LSP update. The notifications are shown in the **Tasks** tab under the Notifications icon that is located next to **Cog** (⚙️).

Overview of Secure Firewall Recommended Rules

You can use intrusion rule recommendations to target vulnerabilities associated with host assets detected in the network. For example, operating systems, servers, and client application protocols. This allows you to tailor your intrusion policy to the specific needs of your monitored network.

The system makes an individual set of recommendations for each intrusion policy. It typically recommends rule state changes for standard text rules and shared object rules. However, it can also recommend changes for inspector and decoder rules.

When you generate rule state recommendations, you can use the default settings or configure advanced settings. Advanced settings allow you to:

- Redefine which hosts on your network the system monitors for vulnerabilities
- Influence which rules the system recommends based on rule overhead
- Specify whether to generate recommendations to disable rules

You can also choose to use the recommendations immediately or review the recommendations (and affected rules) before accepting them.

Choosing to use recommended rule states adds a read-only Secure Firewall Recommendations layer to your intrusion policy, and subsequently choosing not to use recommended rule states removes the layer.

You can schedule a task to generate recommendations automatically based on the most recently saved configuration settings in your intrusion policy.

The system does not change rule states that you set manually such as:

- Manually setting the states of specified rules *before* you generate recommendations prevents the system from modifying the states of those rules in the future.
- Manually setting the states of specified rules *after* you generate recommendations overrides the recommended states of those rules.



Tip The intrusion policy report can include a list of rules with rule states that differ from the recommended state.

While displaying the recommendation-filtered Rules page, or after accessing the Rules page directly from the navigation panel or the Policy Information page, you can manually set rule states, sort rules, and take any of the other actions available on the Rules page, such as suppressing rules, setting rule thresholds, and so on.



Note The Cisco Talos Intelligence Group (Talos) determines the appropriate state of each rule in the system-provided policies. If you use a system-provided policy as your base policy, and you allow the system to set your rules to the Secure Firewall recommended rule state, the rules in your intrusion policy match the settings recommended for your network assets.

Prerequisites for Network Analysis and Intrusion Policies

To allow the Snort inspection engine to process traffic for intrusion and malware analysis, you must have the IPS license enabled for the Threat Defense device.

You must be an Admin user to manage network analysis, intrusion policies, and perform migration tasks.

Generate New Secure Firewall Recommendations in Snort 3

Generate the Secure Firewall recommendations for the intrusion policy and then follow the steps that are listed here to create new recommended rule settings in Snort 3. Rule overheads are interpreted as **security levels** based on the threshold policies selected by you in Snort 3. Recommended action is based on the selected security level and if it is higher than the base policy, then the recommendation is not just limited to generating the events.

Prior to setting the Secure Firewall recommendations you should ask which of the three points listed below closely matches the goal:

- **Increased Protection**—Enable additional rules based on vulnerabilities found in the host database and do not automatically disable any rules. This will likely result in a larger rule set.
- **Focused Protection**—Enable additional rules and disable existing rules based on vulnerabilities found in the host database. This can increase or decrease the number of rules depending on vulnerabilities discovered.
- **Higher Efficiency**—Use the currently enabled rule set and disable any rules for vulnerabilities not found in the host database. This will likely result in a smaller enabled rule set.

Based on the response, the recommendation actions are as follows:

- Set recommendations to the next highest security level, and uncheck the disable rules.
- Set recommendations to the next highest security level, and check the disable rules.
- Set recommendations to the current security level, and check the disable rules.

Before you begin

Secure Firewall recommendations have the following requirements:

- Ensure that hosts are present in the system to generate recommendations.
- Protected networks configured for recommendations should map to the hosts present in the system

Step 1 Choose **Policies > Intrusion**.

Step 2 Click the **Snort 3 Version** button of the intrusion policy.

Step 3 Click the **Recommendations (Not in Use)** layer to configure the rule recommendations. Click **Start**.

In the Secure Firewall Rule Recommendations window you can set the following:

- **Security Level:** Click to select the security level. Optionally, you can check the **Accept Recommendation to Disable Rules** checkbox to disable rules that are not enabled at the input security level and in protected networks. Only enable this option if you need to trim your rule set due to a high number of alerts or to improve inspection performance. The security levels are:

- Security level 1: Connectivity Over Security

No Impact—No new rules are enabled and no existing rules are disabled. To increase the protection, select a higher security level.

Lower Security (checkbox is checked)—All rules are disabled except for the rules in the Connectivity Over Security ruleset that match potential vulnerabilities on discovered hosts. It is recommended instead to adjust the Base Policy.

- Security level 2: Balanced Security Over Connectivity

No Impact—No new rules are enabled and no existing rules are disabled. To increase the protection, select a higher security level.

Higher Efficiency (checkbox is checked)—Keeps existing rules that match potential vulnerabilities on discovered hosts and disables rules for vulnerabilities not found on the network.

- Security level 3: Security Over Connectivity

Increased Security—Enables additional rules that match potential vulnerabilities on discovered hosts based on the Maximum Detection ruleset.

Focused Security (checkbox is checked)—Enables additional rules that match vulnerabilities on discovered hosts based on the Security Over Connectivity ruleset, while disabling existing rules that do not match potential vulnerabilities on discovered hosts.

- Security level 4 : Maximum Detection

Increased Security—Enables additional rules that match potential vulnerabilities on discovered hosts based on the Security Over Connectivity ruleset.

Focused Security (checkbox is checked)—Enables additional rules that match vulnerabilities on discovered hosts based on the Maximum Detection ruleset, while disabling existing rules that do not match potential vulnerabilities on discovered hosts.

Note Maximum Detection enables a very high number of rules and may impact performance. We recommend you to review and test this setting before deploying into a production environment.

- **Protected Networks:** Specifies the monitored networks or individual hosts to examine for recommendations. You can select one or more system or custom defined network objects from the drop-down list. By default, any IPv4 or IPv6 networks are selected, if no selection is done.

Important The Secure Firewall Rule Recommendations depend on network discovery. Protected Networks apply to any hosts discovered within the ranges configured in your Network Discovery policy. For more information, see the chapter [Network Discovery Policies](#) in the *Cisco Secure Firewall Management Center Device Configuration guide*.

Click the **Add +** button to create a new network object of type Host or Network and click **Save**.

Step 4 Generate and apply recommendations:

- **Generate:** Generates the recommendations for an intrusion policy. This action lists the rules under Recommended Rules (Not in use).
- **Generate and Apply:** Generates and applies the recommendations for an intrusion policy. This action lists the rules under Recommended Rules (In use).

Recommendations are generated successfully. A new recommendation tab appears with all the recommended rules with their corresponding recommended actions. Rule action preset filters are also available for this tab, in addition with new recommendations.

Step 5 You can verify the recommendations and then choose to apply them accordingly:

- **Accept**—Applies the previously generated recommendations for an Intrusion policy.
- **Refresh**—Regenerates and updates the rule recommendations for an Intrusion policy.
- **Edit**—It opens the Recommendations dialog box, you can provide the recommendation input values and then generate the recommendations.
- **Remove All**—Revert or remove the applied recommended rules from the policy and also removes the recommendation tab.

Under **All Rules**, there is a Recommended Rules section which displays the recommended rules.

Note Final action for an Intrusion rule is applied based on the rule action priority order and following is the rule action priority order:

Rule Override > Generated Recommendations > Group Override > Base Policy Default Action

For enabled recommendations, management center considers the current state: group overrides, base policy, and recommendation configurations and priority order of actions is:

pass > block > reject > drop > rewrite > alert

What to do next

Deploy configuration changes; see [Deploy Configuration Changes, on page 23](#).



PART II

Advanced Network Analysis in Snort 3

- [Get Started with Snort 3 Network Analysis Policies, on page 63](#)



CHAPTER 6

Get Started with Snort 3 Network Analysis Policies

This chapter provides an insight into network analysis policy basics, prerequisites, and how to manage network analysis policies. It also provides information on custom network analysis policy creation and network analysis policy settings.

- [Overview of Network Analysis Policies, on page 63](#)
- [Manage Network Analysis Policies, on page 64](#)
- [Snort 3 Definitions and Terminologies for Network Analysis Policy, on page 65](#)
- [Prerequisites for Network Analysis and Intrusion Policies, on page 67](#)
- [Custom Network Analysis Policy Creation for Snort 3, on page 67](#)
- [Network Analysis Policy Settings and Cached Changes, on page 94](#)

Overview of Network Analysis Policies

Network analysis policies govern many traffic preprocessing options, and are invoked by advanced settings in your access control policy. Network analysis-related preprocessing occurs after Security Intelligence matching and SSL decryption, but before intrusion or file inspection begins.

By default, the system uses the *Balanced Security and Connectivity* network analysis policy to preprocess all traffic handled by an access control policy. However, you can choose a different default network analysis policy to perform this preprocessing. For your convenience, the system provides a choice of several non-modifiable network analysis policies, which are tuned for a specific balance of security and connectivity by the Cisco Talos Intelligence Group (Talos). You can also create a custom network analysis policy with custom preprocessing settings.



Tip System-provided intrusion and network analysis policies are similarly named but contain different configurations. For example, the Balanced Security and Connectivity network analysis policy and the Balanced Security and Connectivity intrusion policy work together and can both be updated in intrusion rule updates. However, the network analysis policy governs mostly preprocessing options, whereas the intrusion policy governs mostly intrusion rules. Network analysis and intrusion policies work together to examine your traffic.

You can also tailor traffic preprocessing options to specific security zones, networks, and VLANs by creating multiple custom network analysis policies, then assigning them to preprocess different traffic. (Note that ASA FirePOWER cannot restrict preprocessing by VLAN.)

Manage Network Analysis Policies

Under your user name in the toolbar, the system displays a tree of available domains. To switch domains, choose the domain you want to access.

Step 1 Choose one of the following paths to access the network analysis policy.

- **Policies > Access Control**, then click **Network Analysis Policy**
- **Policies > Access Control > Intrusion**, then click **Network Analysis Policies**
- **Policies > Intrusion > Network Analysis Policies**

Note If your custom user role limits access to the first path listed here, use the second path to access the policy.

Step 2 Manage your network analysis policy:

- **Compare**—Click **Compare Policies**; see *Comparing Policies* in the *Cisco Secure Firewall Management Center Configuration Guide*.

Note You can compare Snort 2 policies only.

- **Create**—If you want to create a new network analysis policy, click **Create Policy**.

Two versions of the network analysis policy are created, a **Snort 2 Version** and a **Snort 3 Version**.

- For the Snort 2 version, see *Custom Network Analysis Policy Creation for Snort 2* in the *Cisco Secure Firewall Management Center Configuration Guide*.
- For the Snort 3 version, see [Custom Network Analysis Policy Creation for Snort 3, on page 67](#).

- **Delete**—If you want to delete a network analysis policy, click the **Delete** icon, then confirm that you want to delete the policy. You cannot delete a network analysis policy if an access control policy references it.

If the controls are dimmed, the configuration belongs to an ancestor domain, or you do not have permission to modify the configuration.

- **Edit**—If you want to edit an existing network analysis policy, click the **Edit** icon.

If **View** (👁) appears instead, the configuration belongs to an ancestor domain, or you do not have permission to modify the configuration.

- **Report**—Click the **Report** icon; see *Generating Current Policy Reports* in the *Cisco Secure Firewall Management Center Configuration Guide*.

Snort 3 Definitions and Terminologies for Network Analysis Policy

The following table lists the Snort 3 concepts and terms used in the Network Analysis Policy.

Table 6: Snort 3 Definitions and Terminologies for Network Analysis Policy

Term	Description
Inspectors	Inspectors are plugins that process packets (similar to the Snort 2 preprocessor).
Binder inspector	<p>Binder inspector defines the flow when a particular inspector has to be accessed and taken into consideration.</p> <p>When the traffic matches the conditions defined in the binder inspector, only then do the values/configurations for that inspector come into effect.</p> <p>For more information, see <i>Binder Inspector</i> in Custom Network Analysis Policy Creation for Snort 3, on page 67.</p>
Singleton inspectors	<p>Singleton inspectors contain one instance. These inspectors do not support adding more instances like multiton inspectors. Settings of singleton inspector are applied to the entire traffic matching that inspector and not to a specific traffic segment.</p> <p>For more information, see <i>Singleton Inspectors</i> in Custom Network Analysis Policy Creation for Snort 3, on page 67.</p>
Multiton inspectors	<p>Multiton inspectors contain multiple instances which you can configure as needed. These inspectors support configuring settings based on specific conditions, such as network, port, and VLAN. One set of supported settings is called an instance.</p> <p>For more information, see <i>Multiton Inspectors</i> in Custom Network Analysis Policy Creation for Snort 3, on page 67.</p>

Term	Description
Schema	<p>The schema file is based on the OpenAPI JSON specification, and it validates the content that you upload or download. You can download the schema file and open it using any third-party JSON editor, such as Swagger editor. The schema file helps you to identify what parameters can be configured for inspectors with their corresponding allowed values, range, and accepted patterns to be used.</p> <p>For more information, see Customize the Network Analysis Policy, on page 75.</p>
Sample file	<p>It is a pre-existing template that contains example configurations to help you with configuring the inspectors.</p> <p>You can refer to the example configurations included in the sample file and make any changes that you may require.</p> <p>For more information, see Customize the Network Analysis Policy, on page 75.</p>
Full configuration	<p>You can download the entire inspector configurations in a single file.</p> <p>All information regarding the inspector configuration is available in this file.</p> <p>The full configuration is a merged configuration of the default configuration (rolled out as a part of the LSP updates by Cisco Talos) and the custom NAP inspector configurations.</p> <p>For more information, see Customize the Network Analysis Policy, on page 75.</p>

Term	Description
Overridden configuration	<p>In the Snort 3 Version of the network analysis policy page:</p> <ul style="list-style-type: none"> • Under Actions > Upload, you can click Overridden Configuration to upload the JSON file that contains the overridden configuration. • Under Actions > Download, you can click Overridden Configuration to download the inspector configuration that has been overridden. <p>If you have not overridden any inspector configuration, then this option is disabled. When you override the inspector configuration, then this option is enabled automatically to allow you to download.</p> <p>For more information, see Customize the Network Analysis Policy, on page 75.</p>

Related Topics

[Custom Network Analysis Policy Creation for Snort 3](#), on page 67

[Customize the Network Analysis Policy](#), on page 75

[Network Analysis Policy Mapping](#), on page 72

Prerequisites for Network Analysis and Intrusion Policies

To allow the Snort inspection engine to process traffic for intrusion and malware analysis, you must have the IPS license enabled for the Threat Defense device.

You must be an Admin user to manage network analysis, intrusion policies, and perform migration tasks.

Custom Network Analysis Policy Creation for Snort 3

The default network analysis policy is tuned for typical network requirements and optimal performance. Usually, the default network analysis policy suffices most network requirements and you might not need to customize the policy. However, when you have a specific network requirement or when you are facing performance issues, the default network analysis policy can be customized. Note that customizing the network analysis policy is an advanced configuration that should be done only by advanced users or Cisco support.

Network analysis policy configuration for Snort 3 is a data-driven model, which is based on JSON and JSON Schema. Schema is based on the OpenAPI specification, and it helps you get a view of the supported inspectors, settings, settings type, and valid values. The Snort 3 inspectors are plugins that process packets (similar to the Snort 2 preprocessor). Network analysis policy configuration is available to download in the JSON format.

In Snort 3, the list of inspectors and settings are not in a one-to-one mapping with the Snort 2 list of preprocessors and settings. Also, the number of inspectors and settings available in management center is a subset of the inspectors and settings that Snort 3 supports. See <https://snort.org/snort3> for more information

on Snort 3. See <https://www.cisco.com/go/snort3-inspectors> for more information on the inspectors available in management center.

**Note**

- While upgrading the management center to the 7.0 release, the changes that were done in the Snort 2 version of the network analysis policy are not migrated to Snort 3 after the upgrade.
- Unlike the intrusion policy, there is no option to synchronize Snort 2 network analysis policy settings to Snort 3.

Default Inspector Updates

Lightweight Security Package (LSP) updates may contain new inspectors or modifications to integer ranges for existing inspector configurations. Following the installation of an LSP, new inspectors and/or updated ranges will be available under **Inspectors** in the **Snort 3 Version** of your network analysis policy.

Binder Inspector

Binder inspector defines the flow when a particular inspector has to be accessed and taken into consideration. When the traffic matches the conditions defined in the binder inspector, only then the values/configurations for that inspector come into effect. For example:

For the *imap* inspector, the binder defines the following condition when it has to be accessed. That is when:

- Service is equal to *imap*.
- Role is equal to *any*.

If these conditions are met, then use the type *imap*.

```

185  {
186    "when": {
187      "service": "imap",
188      "role": "any"
189    },
190    "use": {
191      "type": "imap"
192    }
193  },

```

Singleton Inspectors

Singleton inspectors contain a single instance. These inspectors do not support adding more instances like multiton inspectors. Settings of singleton inspector are applied to the entire traffic and not to a specific traffic segment.

For example:

```

{
  "normalizer":{
    "enabled":true,
    "type":"singleton",
    "data":{
      "ip4":{
        "df":true
      }
    }
  }
}

```

Multiton Inspectors

Multiton inspectors contain multiple instances which you can configure as needed. These inspectors support configuring settings based on specific conditions, such as network, port, and VLAN. One set of supported

settings is called an instance. There is a default instance, and you can also add additional instances based on specific conditions. If the traffic matches that condition, the settings from that instance are applied. Otherwise, the settings from the default instance are applied. Also, the name of the default instance is the same as the inspector's name.

For a multiton inspector, when you upload the overridden inspector configuration, you also need to include/define a matching binder condition (conditions under when the inspector has to be accessed or used) for each instance in the JSON file, otherwise, the upload will result in an error. You can also create new instances, but make sure that you include a binder condition for every new instance that you create to avoid errors.

For example:

- Multiton inspector where the default instance is modified.

```
{
  "http_inspect":{
    "enabled":true,
    "type":"multiton",
    "instances":[
      {
        "name":"http_inspect",
        "data":{
          "response_depth":5000
        }
      }
    ]
  }
}
```

- Multiton inspector where the default instance and default binder is modified.

```
{
  "http_inspect":{
    "enabled":true,
    "type":"multiton",
    "instances":[
      {
        "name":"http_inspect",
        "data":{
          "response_depth":5000
        }
      }
    ]
  },
  "binder":{
    "type":"binder",
    "enabled":true,
    "rules":[
      {
        "use":{
          "type":"http_inspect"
        },
        "when":{
          "role":"any",
          "ports":"8080",
          "proto":"tcp",
          "service":"http"
        }
      }
    ]
  }
}
```

- Multiton inspector where a custom instance and a custom binder is added.

```
{
  "http_inspect":{
    "enabled":true,
    "type":"multiton",
    "instances":[
      {
        "name":"http_inspect1",
        "data":{
          "response_depth":5000
        }
      }
    ]
  },
  "binder":{
    "type":"binder",
    "enabled":true,
    "rules":[
      {
        "use":{
          "type":"http_inspect",
          "name":"http_inspect1"
        },
        "when":{
          "role":"any",
          "ports":"8080",
          "proto":"tcp",
          "service":"http"
        }
      }
    ]
  }
}
```

Common Industrial Protocol Safety

Common Industrial Protocol (CIP) Safety is a set of extensions to the CIP that enables the safe operation of devices. It also provides fail-safe communication between different nodes on a CIP network.

The CIP Safety protocol comprises two main components:

- CIP Safety segments—Used in Forward Open messages to exchange safety parameters for the subsequent safety session.
- CIP Safety messages—Used to exchange actual safety information.

The CIP inspector detects and identifies:

- CIP as a service and client
- Payloads, such as CIP Read, CIP Admin, CIP Infrastructure, and CIP Write

The CIP inspector can parse the CIP segments and detect the CIP Safety segments in the Forward Open requests.

To test the CIP Safety feature, you must enable the CIP inspector. See [Detect and Block Safety Segments in CIP Packets](#), on page 72.

Detect and Block Safety Segments in CIP Packets

Use case: To detect and block CIP safety segments while allowing other CIP packets:

- Create a custom network analysis policy called **cip_safety**.
- Create access control rules in your access control policy to block CIP Safety and to allow all other packets.

To test the CIP Safety feature, enable the CIP inspector in the management center and assign it to an access control policy.

-
- Step 1** Go to **Policies > Intrusion > Network Analysis Policies**.
- Step 2** Click the **Snort 3 Version** of the network analysis policy **cip_safety** that you created.
- Step 3** Under **Inspectors**, click **cip** to expand it.
- The default configuration appears in the left column and the overridden configuration appears in the right column under the inspector.
- Step 4** Under **Overridden Configuration** on the right column, click the **Edit Inspector** icon and change the "enabled" field in **cip** from false (default) to true.
- Step 5** Click **OK**.
- Step 6** Click **Save**.
- Step 7** To assign the **cip** inspector to the access control policy, choose **Policies > Access Control > Edit** and choose the **Advanced Settings** option from the **More** drop-down arrow at the end of the packet flow line.
- Step 8** Click **Edit** (✎) next to **Network Analysis and Intrusion Policies**.
- Step 9** In the **Network Analysis and Intrusion Policies** window, choose the access control policy **cip_safety** that you created from the **Default Network Analysis Policy** drop-down list.
- The CIP inspector is now enabled in the management center and you can create the custom access control rules to block CIP Safety and to allow all other CIP packets.
- Step 10** After you send live traffic containing CIP Safety packet flows, go to **Connection Events** to verify that the payload is the expected payload that contains CIP Safety packet logs for the detection and block use case as mentioned in this procedure. **CIP** is detected as an application protocol and client (see the **Application Protocol** and **Client** fields), and **CIP Safety** is shown under the **Web Application** field.
-

Network Analysis Policy Mapping

For network analysis policies, Cisco Talos provides mapping information, which is used to find the corresponding Snort 2 version of the policies for the Snort 3 version.

This mapping ensures that the Snort 3 version of policies has its equivalent Snort 2 version.

View Network Analysis Policy Mapping

-
- Step 1** Go to **Policies > Intrusion > Network Analysis Policies**.

Step 2 Click **NAP Mapping**.

Step 3 Expand the arrow for **View Mappings**.

The Snort 3 network analysis policies that are automatically mapped to a Snort 2 equivalent policy are displayed.

Step 4 Click **OK**.

Create a Network Analysis Policy

All the existing network analysis policies are available in management center with their corresponding Snort 2 and Snort 3 versions. When you create a new network analysis policy, it is created with both the Snort 2 version and the Snort 3 version.

Step 1 Go to **Policies > Intrusion > Network Analysis Policies**.

Step 2 Click **Create Policy**.

Step 3 Enter the **Name** and **Description**.

Step 4 Select a **Base Policy** and click **Save**.

The new network analysis policy is created with its corresponding **Snort 2 Version** and **Snort 3 Version**.

Modify the Network Analysis Policy

You can modify the network analysis policy to change its name, description, or the base policy.

Step 1 Go to **Policies > Intrusion > Network Analysis Policies**.

Step 2 Click **Edit** to change the name, description, inspection mode, or the base policy.

Attention **Detection mode deprecation:** From management center 7.4.0 onwards, for a network analysis policy (NAP), the **Detection** inspection mode is deprecated and will be removed in an upcoming release.

The **Detection** mode was intended to be used as a test mode so that you can enable inspections and see how they behave in your network before setting it to drop traffic, that is, to show traffic that would be dropped.

This behavior is improved where all inspector drops are controlled by the rule state, and you can set each one to generate events. This is done to test them before configuring the rule state to drop traffic. As we now have granular control over traffic drops in Snort 3, the **Detection** mode only adds more complexity to the product and is not needed, so the detection mode is deprecated.

If you change a NAP in **Detection** mode to **Prevention**, the NAP that processes the traffic of intrusion events and have the result "will be dropped" will now be "dropped" and the corresponding traffic will drop the traffic from these events. This is applicable for rules whose GIDs are not 1 or 3. GIDs 1 and 3 are text/compiled rules (typically provided by Talos or from your custom/imported rules) and all other GIDs are inspections for anomalies. These are more uncommon rules to trigger in a network. Changing to **Prevention** mode is unlikely to have any impact on the traffic. You need to just disable the intrusion rule that is applicable for the dropped traffic and set it to just generate or disable.

We recommend you choose **Prevention** as the inspection mode, but if you choose **Prevention**, you cannot revert to **Detection** mode.

Note If you edit the network analysis policy name, description, base policy, and inspection mode, the edits are applied to both the Snort 2 and Snort 3 versions. If you want to change the inspection mode for a specific version, then you can do that from within the network analysis policy page for that respective version.

Step 3 Click **Save**.

Search for an Inspector on the Network Analysis Policy Page

On the Snort 3 version of the network analysis policy page, you may need to search for an inspector by entering any relevant text in the search bar.

Step 1 Go to **Policies > Intrusion > Network Analysis Policies**.

Step 2 Go to the **Snort 3 Version** of the network analysis policy.

Step 3 Enter an inspector's name or any relevant text to search for in the **Search** bar.

All the inspectors matching the text you search for are displayed.

For example, if you enter **pop**, then the pop inspector and the binder inspector are shown as matching results on the screen.

Related Topics

[Examples of Custom Network Analysis Policy Configuration](#), on page 83

[View the List of Inspectors with Overrides](#), on page 80

[Snort 3 Definitions and Terminologies for Network Analysis Policy](#), on page 65

[Customize the Network Analysis Policy](#), on page 75

[Make Inline Edit for an Inspector to Override Configuration](#), on page 78

Copy the Inspector Configuration

You can copy the inspector configuration for the Snort 3 version of the network analysis policy according to your requirements.

Step 1 Go to **Policies > Intrusion > Network Analysis Policies**.

Step 2 Go to the **Snort 3 Version** of the network analysis policy.

Step 3 Under **Inspectors**, expand the required inspector for which you want to copy the configuration.

The default configuration is displayed on the left column and the overridden configuration is displayed on the right column under the inspector.

Step 4 Click the **Copy to clipboard** icon to copy the inspector configuration to the clipboard for one or both of the following.

- **Default Configuration** in the left column
- **Overridden Configuration** in the right column

Step 5 Paste the copied inspector configuration to a JSON editor to make any edits you may require.

Related Topics

[Customize the Network Analysis Policy](#), on page 75

Customize the Network Analysis Policy

You can customize the Snort 3 version of the network analysis policy according to your requirements.

Step 1 Go to **Policies > Intrusion > Network Analysis Policies**.


Step 2 Go to the **Snort 3 Version** of the network analysis policy.

Step 3 Click the **Actions** drop-down menu.

The following options are displayed:

- View Schema
- Download Schema / Download Sample File / Template
- Download Full Configuration
- Download Overridden Configuration
- Upload Overridden Configuration

Step 4 Click **View Schema** to open the schema file directly in a browser.



Step 5 You can download the schema file, sample file / template, full configuration, or overridden configuration as needed. These options provide you an insight about the allowed values, range, and patterns, existing and default inspector configurations, and overridden inspector configurations.


a) Click **Download Schema** to download the schema file.

The schema file validates the content that you upload or download. You can download the schema file and open it using any third-party JSON editor. The schema file helps you to identify what parameters can be configured for inspectors with their corresponding allowed values, range, and accepted patterns to be used.

For example, for the *arp_spoof_snort* inspector, you can configure the hosts. The hosts include the *mac* and *ip* address values. The schema file shows the following accepted pattern for these values.

- **mac – pattern:** `^([0-9A-Fa-f]{2}[:-]){5}([0-9A-Fa-f]{2})$`

- **ip – pattern:** `^([0-9]{1,3}\. [0-9]{1,3}\. [0-9]{1,3}\. [0-9]{1,3})(/[0-9]{1,2}){0,1}$`



You must provide the values, range, patterns according to the accepted ones in the schema file to be able to successfully override the inspector configuration, otherwise, you get an error message.

b) Click **Download Sample File / Template** to use a pre-existing template that contains example configurations to help you with configuring the inspectors.

You can refer to the example configurations included in the sample file and make any changes that you may require.

- c) Click **Download Full Configuration** to download the entire inspector configurations in a single JSON file.

Instead of expanding the inspectors separately, you can download the full configuration to look out for the information you need. All information regarding the inspector configuration is available in this file.

- d) Click **Download Overridden Configuration** to download the inspector configuration that has been overridden.

Step 6

To override the existing configuration, follow the steps.

You can choose to override an inspector configuration using the following ways.

- Make inline edits for an inspector directly on the management center. See the topic **Make Inline Edit for an Inspector to Override Configuration** in the **Getting Started with Network Analysis Policies** chapter of the *Cisco Secure Firewall Management Center Snort 3 Configuration Guide*.
- Continue to follow the current procedure of using the **Actions** drop-down menu to upload the overridden configuration file.

If you chose to make inline edits directly in the management center, then you don't need to follow the current procedure further. Otherwise, you must follow this procedure completely.

- a) Under **Inspectors**, expand the required inspector for which you want to override the default configuration.

The default configuration is displayed on the left column and the overridden configuration is displayed on the right column under the inspector.

You may need to search for an inspector by entering any relevant text in in the search bar.

- b) Click the **Copy to clipboard** icon to copy the default inspector configuration to the clipboard.
- c) Create a JSON file and paste the default configuration in it.
- d) Keep the inspector configuration that you want to override, and remove all the other configuration and instances from the JSON file.

You can also use the **Sample File / Template** to understand how to override the default configuration. This is a sample file that includes JSON snippets explaining how you can customize the network analysis policy for Snort 3.

- e) Make changes to the inspector configuration as needed.

Validate the changes and make sure they conform to the schema file. For multiton inspectors, make sure that the binder conditions for all instances are included in the JSON file. See *Multiton Inspectors* in the topic **Custom Network Analysis Policy Creation for Snort 3** in the *Cisco Secure Firewall Management Center Snort 3 Configuration Guide* for more information.

- f) If you are copying any further default inspector configurations, append that inspector configuration to the existing file that contains the overridden configuration.

Note The copied inspector configuration must comply with the JSON standards.

- g) Save the overridden configuration file to your system.

Step 7

From the **Actions** drop-down menu, choose Upload Overridden Configuration to upload the JSON file that contains the overridden configuration.

Caution Upload only the changes that you require. You should not upload the entire configuration as it makes the overrides sticky in nature and therefore, any subsequent changes to the default configuration as part of the LSP updates would not be applied.

You can drag and drop a file or click to browse to the JSON file saved in your system that contains the overridden inspector configuration.

- **Merge inspector overrides** – Content in the uploaded file is merged with the existing configuration if there is no common inspector. If there are common inspectors, then the content in the uploaded file (for common inspectors) takes precedence over the previous content, and it replaces the previous configuration for those inspectors.
- **Replace inspector overrides** – Removes all previous overrides and replaces them with the new content in the uploaded file.

Attention Choosing this option deletes all the previous overrides. Make an informed decision before you override the configuration using this option.

If any error occurs while uploading the overridden inspectors, you see the error in the **Upload Overridden Configuration File** pop-up window. You can also download the file with the error, fix the error, and reupload the file.

Step 8 In the **Upload Overridden Configuration File** pop-up window, click **Import** to upload the overridden inspector configuration.

After you upload the overridden inspector configuration, you will see an orange icon next to the inspector that signifies that it is an overridden inspector.

Also, the **Overridden Configuration** column under the inspector shows the overridden value.

You can also view all the overridden inspectors using the **Show Overrides Only** checkbox adjacent to the Search bar.

Note Make sure that you always download the overridden configuration, open the JSON file, and append any new changes/overrides to the inspector configurations to this file. This action is needed so that you do not lose the old overridden configurations.

Step 9 (Optional) Take a backup of the overridden configuration file on your system before making any new inspector configuration changes.

Tip We recommend that you take the backup from time to time as you override the inspector configuration.

Related Topics

[Revert Overridden Configuration to Default Configuration](#), on page 80

[View the List of Inspectors with Overrides](#), on page 80

[Search for an Inspector on the Network Analysis Policy Page](#), on page 74

[Copy the Inspector Configuration](#), on page 75

Make Inline Edit for an Inspector to Override Configuration

For the Snort 3 version of the network analysis policy, you can make an inline edit for the inspector configuration to override the configuration according to your requirements.

Alternatively, you can also use the **Actions** drop-down menu to upload the overridden configuration file. See [Customize the Network Analysis Policy](#), on page 75 for more information.

Step 1 Go to **Policies > Intrusion > Network Analysis Policies**.

Step 2 Go to the **Snort 3 Version** of the network analysis policy.

- Step 3** Under **Inspectors**, expand the required inspector for which you want to override the default setting.
- The default configuration is displayed on the left column and the overridden configuration is displayed on the right column under the inspector.
- Step 4** Under the **Overridden Configuration** in the right column, click **Edit Inspector** (Pencil) icon to make changes to the inspector configuration.
- The Override Configuration pop-up appears where you can make the required edits.
- Note**
- Make sure that you keep only those settings that you want to override. If you leave a setting with the same value, that field becomes sticky. This means if that setting is changed in the future by Talos, the current value will be retained.
 - If you are adding or deleting any custom instance, make sure that you add or delete a binder rule for that instance in the binder inspector as well.
- Step 5** Click **OK**.
- If there are any errors according to the JSON standards, it shows you an error message.
- Step 6** Click **Save** to save the changes.
- If the changes conform to the OpenAPI schema specification, the management center allows you to save the configuration, otherwise, the **Error saving overridden configuration** pop-up appears that shows the errors. You can also download the file with the errors.

Related Topics

- [Customize the Network Analysis Policy](#), on page 75
- [Revert Unsaved Changes during Inline Edits](#), on page 79
- [Revert Overridden Configuration to Default Configuration](#), on page 80
- [Examples of Custom Network Analysis Policy Configuration](#), on page 83

Revert Unsaved Changes during Inline Edits

While making inline edits to override the configuration for an inspector, you can revert any unsaved changes. Note that this action reverts all unsaved changes to the most recently saved value, but does not revert the configuration to the default configuration for an inspector.

- Step 1** Go to **Policies > Intrusion > Network Analysis Policies**.
- Step 2** Go to the **Snort 3 Version** of the network analysis policy.
- Step 3** Under **Inspectors**, expand the required inspector for which you want to revert the unsaved changes.
- The default configuration is displayed in the left column and the overridden configuration is displayed in the right column under the inspector.
- Step 4** Under the **Overridden Configuration** on the right column, click the **Cross (X)** icon to revert any unsaved changes for the inspector.
- Alternatively, you can click **Cancel** to cancel the changes.

If you do not have any unsaved changes to the inspector configuration, then this option is not visible.

Related Topics

- [Revert Overridden Configuration to Default Configuration](#), on page 80
- [Make Inline Edit for an Inspector to Override Configuration](#), on page 78

View the List of Inspectors with Overrides

You can view a list of all the overridden inspectors.

-
- Step 1** Go to **Policies > Intrusion > Network Analysis Policies**.
 - Step 2** Go to the **Snort 3 Version** of the network analysis policy.
 - Step 3** Check the **Show Overrides Only** checkbox adjacent to the Search bar to view the list of overridden inspectors. All the overridden inspectors are shown with an orange icon next to their names to help you identify them.

Related Topics

- [Search for an Inspector on the Network Analysis Policy Page](#), on page 74
- [Make Inline Edit for an Inspector to Override Configuration](#), on page 78
- [Customize the Network Analysis Policy](#), on page 75

Revert Overridden Configuration to Default Configuration

You can revert any changes that you made to override the default configuration for an inspector. This action reverts the overridden configuration to the default configuration for an inspector.

-
- Step 1** Go to **Policies > Intrusion > Network Analysis Policies**.
 - Step 2** Go to the **Snort 3 Version** of the network analysis policy.
 - Step 3** Under **Inspectors**, expand the required inspector for which you want to revert the overridden configuration.

The overridden inspectors are shown with the orange icon next to their name.

The default configuration is displayed on the left column and the overridden configuration is displayed on the right column under the inspector. Under the **Overridden Configuration** on the right column, click **Revert to default configuration** (back arrow) icon to revert the overridden configuration for the inspector to the default configuration.

If you did not make any changes to the default configuration for the inspector, then this option is disabled.

- Step 4** Click **Revert** to confirm the decision.
- Step 5** Click **Save** to save the changes.

If you do not want to save the changes, you can click **Cancel** or the **Cross (X)** icon.

Related Topics

- [Revert Unsaved Changes during Inline Edits](#), on page 79

[Customize the Network Analysis Policy](#), on page 75

[Make Inline Edit for an Inspector to Override Configuration](#), on page 78

[Examples of Custom Network Analysis Policy Configuration](#), on page 83

Validate Snort 3 Policies

To validate the Snort 3 policies, here is a list of basic information that user can make note of:

- Current version of the management center can manage multiple threat defense versions.
- Current version of management center supports NAP configurations which are not applicable to previous version of threat defense devices.
- Current NAP Policy and validations will work based on the current version support.
- Changes may include content which is not valid for previous versions of threat defenses.
- Policy configuration changes are accepted if they are valid configuration for the current version and which is performed using current Snort 3 binary and NAP schema.
- For previous version threat defenses, validation is performed during deployment using NAP schema and Snort 3 binary for that specific version. If there is any configuration which is not applicable for the given version, user is provided information or warning that we will not deploy the configuration which is not supported on the given version and remaining configuration will get deployed.

In this procedure, when we associate the NAP policy to an Access Control Policy and deploy it on a device, for example any inspector like rate filter configuration is applied to validate the Snort 3 policies.

-
- Step 1** **Steps to Override NAP Policy Configuration:** Under **Inspectors** in the **Snort 3 Version** of the network analysis policy, expand the required inspector for which you want to override the default setting.
- The default configuration is displayed on the left column and the overridden configuration is displayed on the right column under the inspector.
- Step 2** Under the **Overridden Configuration** on the right column, click **Edit Inspector** (Pencil) icon to make changes to any inspector like `rate_filter`.
- The Override Configuration pop-up appears where you can make the required edits to the `rate_filter` inspector.
- Step 3** Click **OK**.
- Step 4** Click **Save** to save the changes.
- Alternatively, you can also use the **Actions** drop-down menu to upload the overridden configuration file.
- Step 5** Click the **Actions** drop-down menu in the **Snort 3 Version** of the network analysis policy.
- Step 6** Under **Upload** you can click **Overridden Configuration** to upload the JSON file that contains the overridden configuration.
- Caution** Upload only the changes that you require. You should not upload the entire configuration as it makes the overrides sticky in nature and therefore, any subsequent changes to the default configuration as part of the LSP updates will not be applied.

You can drag and drop a file or click to browse to the JSON file saved in your system that contains the overridden inspector configuration.

- **Merge inspector overrides** – Content in the uploaded file is merged with the existing configuration if there is no common inspector. If there are common inspectors, then the content in the uploaded file (for common inspectors) takes precedence over the previous content, and it replaces the previous configuration for those inspectors.
- **Replace inspector overrides** – Removes all previous overrides and replaces them with the new content in the uploaded file.

Attention As choosing this option deletes all the previous overrides, make an informed decision before you override the configuration using this option.

If any error occurs while uploading the overridden inspectors, you see the error on the **Upload Overridden Configuration File** pop-up window. You can also download the file with the error, then fix the error and reupload the file.

- Step 7** **Steps to Associate NAP Policy to Access Control Policy:** In the access control policy editor, click **Advanced**, then click **Edit** next to the Network Analysis and Intrusion Policies section.
- Step 8** From the **Default Network Analysis Policy** drop-down list, select a default network analysis policy.
- If you choose a user-created policy, you can click **Edit** to edit the policy in a new window. You cannot edit system-provided policies.
- Step 9** Click **OK**.
- Step 10** Click **Save** to save the policy.
- Step 11** Alternatively, in the access control policy editor, click **Advanced**, then click **Edit** next to the Network Analysis and Intrusion Policies section.
- Step 12** Click **Add Rule**.
- Step 13** Configure the rule's conditions by clicking the conditions you want to add.
- Step 14** Click **Network Analysis** and choose the **Network Analysis Policy** you want to use to preprocess the traffic matching this rule.
- Step 15** Click **Add**.
- Step 16** **Deployment:** On the management center menu bar, click **Deploy** and then select **Deployment**.
- Step 17** Identify and choose the devices on which you want to deploy configuration changes.
- Search—Search for the device name, type, domain, group, or status in the search box.
 - Expand—Click **Expand Arrow** to view device-specific configuration changes to be deployed.
- By selecting the device check box, all the changes for the device, which are listed under the device, are pushed for deployment. However, you can use the **Policy Selection** to select individual policies or configurations to deploy while withholding the remaining changes without deploying them.
- Optionally, use **Show or Hide Policy** to selectively view or hide the associated unmodified policies.
- Step 18** Click **Deploy**.
- Step 19** If the system identifies errors or warnings in the changes to be deployed, it displays them in the **Validation Messages** window. To view complete details, click the arrow icon before the warnings or errors.
- Note** It shows a warning that Snort 3 Network analysis policy contains inspectors or attributes that are not valid for this threat defense version, following the invalid settings will be skipped in deployment: Invalid inspectors are : [“rate_filter”] only for devices lower than 7.1 version.

Examples of Custom Network Analysis Policy Configuration

This is a sample file that includes JSON snippets explaining how you can customize the network analysis policy for Snort 3. You can choose to override an inspector configuration using the following ways:

- Make inline edits for an inspector directly on the management center. See [Make Inline Edit for an Inspector to Override Configuration, on page 78](#).
- Use the **Actions** drop-down menu to upload the overridden configuration file. See [Customize the Network Analysis Policy, on page 75](#).

Before you choose any of these options, review all the following details and examples that will help you in defining the network analysis policy overrides successfully. You must read and understand the examples for various scenarios explained here to avoid any risks and errors.

If you choose to override an inspector configuration from the **Actions** drop-down menu, you need to construct a JSON file for the network analysis policy overrides and upload the file.

For overriding an inspector configuration in the network analysis policy, you must upload only the changes that you require. You should not upload the entire configuration because it makes the overrides sticky in nature and therefore, any subsequent changes to the default values or configuration as part of the LSP updates would not be applied.

Here are the examples for various scenarios:

Enabling a Singleton Inspector when the Default State in the Base Policy is Disabled

```
{
  "rate_filter": {
    "enabled": true,
    "type": "singleton",
    "data": []
  }
}
```

Disabling a Singleton Inspector when the Default State in the Base Policy is Enabled

```
{
  "rate_filter": {
    "enabled": false,
    "type": "singleton",
    "data": []
  }
}
```

Enabling a Multiton Inspector when the Default State in the Base Policy is Disabled

```
{
  "ssh": {
    "enabled": true,
    "type": "multiton",
    "instances": []
  }
}
```

Disabling a Multiton Inspector when the Default State in the Base Policy is Enabled

```
{
  "ssh": {
```

```

    "enabled": false,
    "type": "multiton",
    "instances": []
  },
  "iecl04": {
    "type": "multiton",
    "enabled": false,
    "instances": []
  }
}

```

Overriding the Default Value of Specific Setting(s) for Singleton Inspector

```

{
  "normalizer": {
    "enabled": true,
    "type": "singleton",
    "data": {
      "tcp": {
        "block": true
      },
      "ip6": true
    }
  }
}

```

Overriding Specific Setting(s) of a Default Instance (where Instance Name Matches with Inspector Type) in Multiton Inspector

```

{
  "http_inspect": {
    "enabled": true,
    "type": "multiton",
    "instances": [
      {
        "data": {
          "unzip": false
        },
        "name": "http_inspect"
      }
    ]
  }
}

```

Adding Binder Rule for a Default Instance with Required Changes



Note Default binder rules can't be edited, they are always appended at the end.

```

{
  "binder": {
    "enabled": true,
    "type": "binder",
    "rules": [
      {
        "use": {
          "type": "http_inspect"
        },
        "when": {
          "role": "server",

```

```

        "service": "http",
        "dst_nets": "10.1.1.0/24"
    }
  ]
}

```

Adding a New Custom Instance



Note Corresponding binder rule entry must be defined in the binder inspector.

```

{
  "telnet": {
    "enabled": true,
    "type": "multiton",
    "instances": [
      {
        "name": "telnet_my_instance",
        "data": {
          "encrypted_traffic": true
        }
      }
    ]
  },
  "binder": {
    "enabled": true,
    "type": "binder",
    "rules": [
      {
        "when": {
          "role": "any",
          "service": "telnet"
        },
        "use": {
          "type": "telnet",
          "name": "telnet_my_instance"
        }
      }
    ]
  }
}

```

Overriding a Singleton Instance, Multiton Default Instance, and Creating a New Multiton Instance in a Single JSON Override

Example to show the following in a single JSON override:

- Overriding a Singleton instance (**normalizer** inspector)
- Overriding a Multiton default instance (**http_inspect** inspector)
- Creating a new Multiton instance (**telnet** inspector)

```

{
  "normalizer": {
    "enabled": true,
    "type": "singleton",
    "data": {

```

```

        "tcp": {
            "block": true
        },
        "ip6": true
    }
},
"http_inspect": {
    "enabled": true,
    "type": "multiton",
    "instances": [
        {
            "data": {
                "unzip": false,
                "xff_headers": "x-forwarded-for true-client-ip x-another-forwarding-header"
            },
            "name": "http_inspect"
        }
    ]
},
"telnet": {
    "enabled": true,
    "type": "multiton",
    "instances": [
        {
            "name": "telnet_my_instance",
            "data": {
                "encrypted_traffic": true
            }
        }
    ]
},
"binder": {
    "enabled": true,
    "type": "binder",
    "rules": [
        {
            "when": {
                "role": "any",
                "service": "telnet"
            },
            "use": {
                "type": "telnet",
                "name": "telnet_my_instance"
            }
        },
        {
            "use": {
                "type": "http_inspect"
            },
            "when": {
                "role": "server",
                "service": "http",
                "dst_nets": "10.1.1.0/24"
            }
        }
    ]
}
}

```



Note You don't need to give the **name** attribute for the default instance in binder rules.

Configuring arp_spoof

Example for configuring `arp_spoof`:

The `arp_spoof` inspector does not have any default configurations for any attributes. This demonstrates the case where you can provide the overrides.

```
{
  "arp_spoof": {
    "type": "singleton",
    "data": {
      "hosts": [
        {
          "ip": "1.1.1.1",
          "mac": "ff:0f:f1:0f:0f:ff"
        },
        {
          "ip": "2.2.2.2",
          "mac": "ff:0f:f2:0f:0f:ff"
        }
      ]
    },
    "enabled": true
  }
}
```

Configuring rate_filter

```
{
  "rate_filter": {
    "data": [
      {
        "apply_to": "[10.1.2.100, 10.1.2.101]",
        "count": 5,
        "gid": 135,
        "new_action": "alert",
        "seconds": 1,
        "sid": 1,
        "timeout": 5,
        "track": "by_src"
      }
    ],
    "enabled": true,
    "type": "singleton"
  }
}
```

Configuring Binder Rules when Multi-Hierarchy Network Analysis Policy is Used

This example illustrates adding a new custom instance in child policy and the way binder rules should be written. Binder rules are defined as a list and therefore, it is important to pick up the rules defined in the parent policy and build the new rules on top of it as rules will not be merged automatically. The binder rules available in child policy are a source of truth in totality.

On the threat defense, the default Cisco Talos policy rules are appended on these user-defined overrides.

Parent Policy:

We have defined a custom instance by the name `telnet_parent_instance` and the corresponding binder rule.

```
{
  "telnet": {
```

```

    "type": "multiton",
    "instances": [
      {
        "data": {
          "normalize": true,
          "encrypted_traffic": true
        },
        "name": "telnet_parent_instance"
      }
    ],
    "enabled": true
  },
  "binder": {
    "enabled": true,
    "type": "binder",
    "rules": [
      {
        "when": {
          "role": "any",
          "service": "telnet"
        },
        "use": {
          "type": "telnet",
          "name": "telnet_parent_instance"
        }
      }
    ]
  }
}

```

Child Policy:

This network analysis policy has the aforementioned policy as its base policy. We have defined a custom instance by the name **telnet_child_instance** and have also defined the binder rules for this instance. The binder rules from parent policy need to be copied here, and then child policy binder rules can be prepended or appended on top of it based on the nature of the rule.

```

{
  "telnet": {
    "type": "multiton",
    "instances": [
      {
        "data": {
          "normalize": true,
          "encrypted_traffic": false
        },
        "name": "telnet_child_instance"
      }
    ],
    "enabled": true
  },
  "binder": {
    "enabled": true,
    "type": "binder",
    "rules": [
      {
        "when": {
          "role": "any",
          "service": "telnet",
          "nets": "10.2.2.0/24"
        },
        "use": {
          "type": "telnet",
          "name": "telnet_child_instance"
        }
      }
    ]
  }
}

```



```

    }
  },
  {
    "when": {
      "role": "any",
      "service": "telnet"
    },
    "use": {
      "type": "telnet",
      "name": "telnet_parent_instance"
    }
  }
]
}
}

```

Configuring List Inspector Attribute in General

While changing overrides for any attribute of type list, it is important to pass the full contents rather than partial override. This means if a base policy attributes are defined as:

```

{
  "list-attribute": [
    {
      "entry1": {
        "key1": "value1"
      }
    },
    {
      "entry2": {
        "key2": "value2"
      }
    }
  ]
}

```

If you want to modify **value1** to **value1-new**, the override payload must look like the following:

Correct Way:

```

{
  "list-attribute": [
    {
      "entry1": {
        "key1": "value1-new"
      }
    },
    {
      "entry2": {
        "key2": "value2"
      }
    }
  ]
}

```

Incorrect Way:

```

{
  "list-attribute": [
    {
      "entry1": {
        "key1": "value1-new"
      }
    }
  ]
}

```

```

]
}

```

You can understand this configuration by taking the trimmed values of the `alt_max_command_line_len` attribute in the `smtp` inspector. Suppose the default (base) policy configuration for `smtp` inspector is as follows:

```

{
  "smtp": {
    "type": "multiton",
    "instances": [
      {
        "name": "smtp",
        "data": {
          "decompress_zip": false,
          "normalize_cmds": "ATRN AUTH BDAT CHUNKING DATA DEBUG EHLO
EMAL ESAM ESND ESOM ETRN EVFY EXPN HELO HELP IDENT MAIL
NOOP ONEX QUEU QUIT RCPT RSET SAML SEND SOML STARTTLS TICK
TIME TURN TURNME VERB VRFY X-ADAT XADR XAUTH XCIR X-DRCP X-
ERCP XEXCH50 X-EXCH50 X-EXPS XGEN XLICENSE X-LINK2STATE XQUE
XSTA XTRN XUSR",
          "ignore_data": false,
          "max_command_line_len": 512,
          "max_header_line_len": 1000,
          "log_rcptto": false,
          "decompress_swf": false,
          "max_response_line_len": 512,
          "b64_decode_depth": -1,
          "max_auth_command_line_len": 1000,
          "log_email_hdrs": false,
          "xlink2state": "alert",
          "binary_data_cmds": "BDAT XEXCH50",
          "auth_cmds": "AUTH XAUTH X-EXPS",
          "log_filename": false,
          "uu_decode_depth": -1,
          "ignore_tls_data": false,
          "data_cmds": "DATA",
          "bitenc_decode_depth": -1,
          "alt_max_command_line_len": [
            {
              "length": 255,
              "command": "ATRN"
            },
            {
              "command": "AUTH",
              "length": 246
            },
            {
              "length": 255,
              "command": "BDAT"
            },
            {
              "length": 246,
              "command": "DATA"
            }
          ],
          "log_mailfrom": false,
          "decompress_pdf": false,
          "normalize": "none",
          "email_hdrs_log_depth": 1464,
          "valid_cmds": "ATRN AUTH BDAT CHUNKING DATA DEBUG EHLO
EMAL ESAM ESND ESOM ETRN EVFY EXPN HELO HELP IDENT MAIL
NOOP ONEX QUEU QUIT RCPT RSET SAML SEND SOML STARTTLS TICK
TIME TURN TURNME VERB VRFY X-ADAT XADR XAUTH XCIR X-DRCP X-

```

```

        ERCP XEXCH50 X-EXCH50 X-EXPS XGEN XLICENSE X-LINK2STATE XQUE
        XSTA XTRN XUSR",
        "qp_decode_depth": -1
    }
  ],
  "enabled": true
}

```

Now, if you want to add two more objects to the `alt_max_command_line_len` list:

```

{
  "length": 246,
  "command": "XEXCH50"
},
{
  "length": 246,
  "command": "X-EXPS"
}

```

Then the custom network analysis policy override JSON would look like the following:

```

{
  "smtp": {
    "type": "multiton",
    "instances": [
      {
        "name": "smtp",
        "data": {
          "alt_max_command_line_len": [
            {
              "length": 255,
              "command": "ATRNL"
            },
            {
              "command": "AUTH",
              "length": 246
            },
            {
              "length": 255,
              "command": "BDAT"
            },
            {
              "length": 246,
              "command": "DATA"
            },
            {
              "length": 246,
              "command": "XEXCH50"
            },
            {
              "length": 246,
              "command": "X-EXPS"
            }
          ]
        }
      }
    ]
  },
  "enabled": true
}

```

Configuring Overrides when Multi-Hierarchy Network Analysis Policy is used in Multiton Inspector

This example illustrates overriding attributes in child policy and how the merged configuration will be used in the child policy for any instance. Any overrides defined in the child policy will be merged with the parent policy. Thus, if attribute1 and attribute2 are overridden in parent policy and attribute2 and attribute3 are overridden in the child policy, the merged configurations are for child policy. This means that attribute1 (defined in parent policy), attribute2 (defined in child policy), and attribute3 (defined in child policy) will be configured on the device.

Parent Policy:

Here we have defined a custom instance by the name `telnet_parent_instance` and overridden 2 attributes namely, `normalize` and `encrypted_traffic` in the custom instance.

```
{
  "telnet": {
    "type": "multiton",
    "instances": [
      {
        "data": {
          "normalize": true,
          "encrypted_traffic": false
        },
        "name": "telnet_parent_instance"
      }
    ],
    "enabled": true
  },
  "binder": {
    "enabled": true,
    "type": "binder",
    "rules": [
      {
        "when": {
          "role": "any",
          "service": "telnet"
        },
        "use": {
          "type": "telnet",
          "name": "telnet_parent_instance"
        }
      }
    ]
  }
}
```

Child Policy:

This network analysis policy has the aforementioned policy as its base policy. We have overridden attribute `encrypted_traffic` from parent policy and also overridden new attribute `ayt_attack_thresh`.

```
{
  "telnet": {
    "type": "multiton",
    "instances": [
      {
        "data": {
          "encrypted_traffic": true,
          "ayt_attack_thresh": 1
        },
        "name": "telnet_parent_instance"
      }
    ],
    "enabled": true
  }
}
```

```
}
}
```

With the above policy JSON, when you deploy the network analysis policy the following merged JSON will be configured on the device.

```
{
  "telnet": {
    "type": "multiton",
    "instances": [
      {
        "data": {
          "normalize": true,
          "encrypted_traffic": true,
          "ayt_attack_thresh": 1
        },
        "name": "telnet_parent_instance"
      }
    ],
    "enabled": true
  },
  "binder": {
    "enabled": true,
    "type": "binder",
    "rules": [
      {
        "when": {
          "role": "any",
          "service": "telnet"
        },
        "use": {
          "type": "telnet",
          "name": "telnet_parent_instance"
        }
      }
    ]
  }
}
```

This example illustrates details for the custom network analysis policy. The same behavior is also exhibited in the default instance. Also, a similar merging would be done for Singleton inspectors.

Removing all the Inspector Overrides for the Network Analysis Policy:

Whenever you want to remove all the overrides for a specific network analysis policy, you can upload an empty JSON. While uploading the overrides, choose the option **Replace inspector overrides**.

```
{
}
```

Related Topics

[Snort 3 Definitions and Terminologies for Network Analysis Policy](#), on page 65

[Network Analysis Policy Mapping](#), on page 72

[Custom Network Analysis Policy Creation for Snort 3](#), on page 67

[Search for an Inspector on the Network Analysis Policy Page](#), on page 74

[Copy the Inspector Configuration](#), on page 75

[Customize the Network Analysis Policy](#), on page 75

[View the List of Inspectors with Overrides](#), on page 80

Network Analysis Policy Settings and Cached Changes

When you create a new network analysis policy, it has the same settings as its base policy.

When tailoring a network analysis policy, especially when disabling inspectors, keep in mind that some inspectors and intrusion rules require that traffic first be decoded or preprocessed in a certain way. If you disable a required inspector, the system automatically uses it with its current settings, although the inspector remains disabled in the network analysis policy web interface.



Note Because preprocessing and intrusion inspection are so closely related, the network analysis and intrusion policies examining a single packet **must** complement each other. Tailoring preprocessing, especially using multiple custom network analysis policies, is an **advanced** task.

The system caches one network analysis policy per user. While editing a network analysis policy, if you select any menu or other path to another page, your changes stay in the system cache even if you leave the page.



PART **III**

Encrypted Visibility Engine for Snort 3

- [Encrypted Visibility Engine, on page 97](#)



CHAPTER 7

Encrypted Visibility Engine

Encrypted Visibility Engine (EVE) is used to identify client applications and processes utilizing TLS encryption. It enables visibility and allows administrators to take actions and enforce policy within their environments. The EVE technology can also be used to identify and stop malware.

- [Overview of Encrypted Visibility Engine, on page 97](#)
- [How EVE Works, on page 98](#)
- [Indications of Compromise Events, on page 98](#)
- [QUIC Fingerprinting in EVE, on page 99](#)
- [Configure EVE, on page 99](#)

Overview of Encrypted Visibility Engine

The encrypted visibility engine (EVE) is used to provide more visibility into the encrypted sessions without the need to decrypt them. These insights into encrypted sessions are obtained by Cisco's open-source library that is packaged in Cisco's vulnerability database (VDB). The library fingerprints and analyzes incoming encrypted sessions and matches it against a set of known fingerprints. This database of known fingerprints is also available in the Cisco VDB.



Note The encrypted visibility engine feature is supported only on management center-managed devices running Snort 3. This feature is not supported on Snort 2 devices, device manager-managed devices, or CDO.

Some of the important features of EVE are the following:

- You can take access control policy actions on the traffic using information derived from EVE.
- The VDB included in Cisco Secure Firewall has the ability to assign applications to some processes detected by EVE with a high confidence value. Alternatively, you can create custom application detectors to:
 - Map EVE-detected processes to new user-defined applications.
 - Override the built-in value of process confidence that is used to assign applications to EVE-detected processes.

See the **Configuring Custom Application Detectors** and **Specifying EVE Process Assignments** sections in the **Application Detection** chapter of the [Cisco Secure Firewall Management Center Device Configuration Guide](#).

- EVE can detect the operating system type and version of the client that created a Client Hello packet in the encrypted traffic.
- EVE supports fingerprinting and analysis of Quick UDP Internet Connections (QUIC) traffic too. The server name from the Client Hello packet is displayed in the URL field of the **Connection Events** page.



Attention To use EVE on management center, you must have a valid IPS license on your device. In the absence of a IPS license, the policy displays a warning and deployment is not allowed.



Note EVE can detect the operating system type and version of SSL sessions. Normal usage of the operating system, such as running applications and package management software, can trigger OS detection. To view client OS detection, in addition to enabling the EVE toggle button, you must enable **Hosts** under **Policies > Network Discovery**. To view a list of possible operating systems on the host IP address, click **Analysis > Hosts > Network Map**, and then choose the required host.

Related Links

[Configure EVE, on page 99](#)

How EVE Works

The encrypted visibility engine (EVE) inspects the Client Hello portion of the TLS handshake to identify client processes. The Client Hello is the initial data packet that is sent to the server. This gives a good indication of the client process on the host. This fingerprint, combined with other data such as destination IP address, provides the basis for EVE's application identification. By identifying specific application fingerprints in the TLS session establishment, the system can identify the client process and take appropriate action (allow/block).

EVE can identify over 5,000 client processes. The system maps a number of these processes to client applications for use as criteria in access control rules. This gives the system the ability to identify and control these applications without enabling TLS decryption. By using fingerprints of known malicious processes, EVE technology can also be used to identify and block encrypted malicious traffic without outbound decryption.

Through machine learning (ML) technology, Cisco processes over one billion TLS fingerprints and over 10000 malware samples daily to create and update EVE fingerprints. These updates are then delivered to customers using Cisco's Vulnerability Database (VDB) packages.

Indications of Compromise Events

The host's Indications of Compromise (IoC) events for encrypted visibility engine detection allows you to check connection events with a very high malware confidence level, as reported by EVE. IoC events are triggered for encrypted sessions generated from a host using a malicious client. You can view information, such as IP address, MAC address, and OS information of the malicious host, and the timestamp of the suspicious activity.

A session with Encrypted Visibility Threat Confidence score 'Very High' as seen in connection events generates an IoC event. You must enable **Hosts** from **Policies > Network Discovery**. In the management center, you can view the IoC event existence from:

- **Analysis > Indications of Compromise**.
- **Analysis > Network Map > Indications of Compromise** > Choose the host that must be checked.

You can view the process information of the session that generated the IoC from:

Analysis > Connection Events > Table View of Connection Events > IoC column. Note that you must manually select the Encrypted Visibility fields and IoC field.

QUIC Fingerprinting in EVE

Snort can identify client applications in Quick UDP Internet Connections (QUIC sessions) based on EVE. QUIC fingerprinting can:

- Detect applications over QUIC without enabling decryption.
- Identify malware without enabling decryption.
- Detect service applications. You can assign access control rules based on the service detected over the QUIC protocol.

Configure EVE

-
- Step 1** Choose **Policies > Access Control**.
 - Step 2** Click **Edit** (✎) next to the access control policy you want to edit.
 - Step 3** Choose **Advanced Settings** from the **More** drop-down arrow at the end of the packet flow line.
 - Step 4** Click **Edit** (✎) next to **Encrypted Visibility Engine**.
 - Step 5** In the **Encrypted Visibility Engine** page, enable the **Encrypted Visibility Engine (EVE)** toggle button.
 - Step 6** **Use EVE for Application Detection**—This toggle button is enabled by default, which means that EVE is allowed to assign client applications to processes.

EVE's fingerprint information is added in the **Encrypted Visibility Fingerprint** column header of the connection events or unified events. For further analysis of the EVE data collected, you can right-click the fingerprint information to open a dropdown menu. In the menu, click **View Encrypted Visibility Engine Process Analysis** to go to appid.cisco.com and view details, such as the fingerprint, VDB version, and so on. Different rows with the same fingerprint string and potential process names associated with them and their prevalence are displayed. Prevalence indicates the frequency of a process associated with a particular fingerprint in the data collection system. You can choose the process names and click **Submit Request** to give feedback about any discrepancy in EVE's process detection. For example, you can submit requests if the process name that is detected does not match with the traffic that is being sent or if the process name is not detected at all for a particular fingerprint.

If you disable the **Use EVE for Application Detection** toggle button:

- AppID-identified clients are assigned to processes and you can see the EVE process and score, but there is no mapping of EVE-detected processes to applications and no action is taken. You can see the details of the events

under **Connection Events** or **Unified Events**. To see the difference in connection events (with and without application assignment), see the **Client Application** column header.

- The **Encrypted Visibility Fingerprint** field in the connection events or unified events is empty.

Step 7 Enable the **Block Traffic Based on EVE Score** toggle button to block traffic based on EVE's threat confidence score. Any incoming traffic that is a potential threat is blocked by default.

The default block threshold is 99 percent, which means:

- If EVE detects the traffic to be malware with 99 percent confidence or more, the traffic is blocked.
- If EVE detects the traffic to be malware with less than 99 percent confidence, EVE takes no action.

Note If EVE has blocked the traffic, in the **Connection Events** page, the **Reason** column header displays **Encrypted Visibility Block**.

Step 8 Use the slider to adjust the threshold for blocking based on EVE's threat confidence, which ranges from **Very Low** to **Very High**.

Step 9 For further granular control, enable the **Advanced Mode** toggle button. Now, you can assign a specific EVE Threat Confidence Score for blocking traffic. The default block threshold is 99 percent.

Caution We recommend that you do not set a threshold below 50 percent to ensure optimal performance.

Step 10 Click **OK**.

Step 11 Click **Save**.

What to do next

Deploy configuration changes.

View EVE Events

After enabling the **Encrypted Visibility Engine** and deploying your access control policy, you can start sending live traffic through your system. You can view the logged connection events in the **Connection Events** page. To access the connection events, in the management center:

Step 1 Click **Analysis > Connections > Events**.

Step 2 Click the **Table View of Connection Events** tab.

You can also view the connection event fields in the **Unified Events** viewer, which is under the **Analysis** menu.

Encrypted Visibility Engine can identify the client process that initiated a connection, the OS on the client, and if the process contains malware or not.

Step 3 In the **Connection Events** page, view the following columns that are added for Encrypted Visibility Engine. Note that you must explicitly enable the mentioned columns.

- Encrypted Visibility Process Name
- Encrypted Visibility Process Confidence Score

- Encrypted Visibility Threat Confidence
- Encrypted Visibility Threat Confidence Score
- Detection Type

For information about these fields, see the section **Connection and Security Intelligence Event Fields** in the **Connection and Security-Related Connection Events** chapter of the [Cisco Secure Firewall Management Center Administration Guide](#).

Note In the **Connection Events** page, if processes are assigned applications, the **Detection Type** column displays **Encrypted Visibility Engine** indicating that the client application was identified by EVE. Without application assignments to process names, the **Detection Type** column displays **AppID** indicating that the engine that identified the client application was AppID.

View EVE Dashboard

You can view the EVE analysis information in two dashboards. To access the dashboards:

-
- Step 1** Under **Overview > Dashboards**, click **Dashboard**.
- Step 2** In the **Summary Dashboard** window, click the **switch dashboard** link and choose **Application Statistics** from the dropdown box.
- Step 3** Choose the **Encrypted Visibility Engine** tab to view the following two dashboards:
- **Top Encrypted Visibility Engine Discovered Processes**—Displays the top TLS process names being used in your network and the connection count. You can click the process name in the table to see the filtered view of the **Connection Events** page, which is filtered by the process name.
 - **Connections by Encrypted Visibility Engine Threat Confidence**—Displays the connections by the confidence levels (Very High, Very Low, and so on). You can click the Threat confidence level in the table to see the filtered view of the **Connection Events** page, which is filtered by the confidence level.
-



PART **IV**

Elephant Flow Detection for Snort 3

- [Elephant Flow Detection, on page 105](#)



CHAPTER 8

Elephant Flow Detection

Elephant flows are extremely large (in total bytes), continuous flows set up by a TCP (or other protocols) flow measured over a network link. By default, elephant flows are those larger than 1 GB/10 seconds. They can cause performance duress in Snort cores. Elephant flows are not numerous, but they can occupy a disproportionate share of the total bandwidth over a period of time. They can lead to problems, such as high CPU utilization, packet drops, and so on.

From management center 7.2.0 onwards (Snort 3 devices only), you can use the elephant flow feature to detect and remediate elephant flows, which helps to reduce system stress and resolve the mentioned issues.

- [About Elephant Flow Detection and Remediation, on page 105](#)
- [Elephant Flow Upgrade from Intelligent Application Bypass, on page 105](#)
- [Configure Elephant Flow, on page 106](#)

About Elephant Flow Detection and Remediation

You can use the elephant flow detection feature to detect and remediate elephant flows. The following remediation actions can be applied:

- **Bypass elephant flow**—You can configure elephant flow to bypass Snort inspection. If this is configured, Snort does not receive any packet from that flow.
- **Throttle elephant flow**—You can apply rate-limit to the flow and continue to inspect flows. The flow rate is calculated dynamically and 10% of the flow rate is reduced. Snort sends the verdict (QoS flow with 10% less flow rate) to the firewall engine. If you choose to bypass all applications including unidentified applications, you cannot configure the throttle action (rate-limit) for any flow.



Note For the elephant flow detection to work, Snort 3 must be the detection engine.

Elephant Flow Upgrade from Intelligent Application Bypass

Intelligent Application Bypass (IAB) is deprecated from version 7.2.0 onwards for Snort 3 devices.

For devices running 7.2.0 or later, you must configure elephant flow settings under the **Elephant Flow Settings** section in the AC policy (Advanced settings tab).

Post-upgrade to 7.2.0 (or later), if you are using a Snort 3 device, the elephant flow configuration settings will be picked and deployed from the **Elephant Flow Settings** section and not from the **Intelligent Application Bypass Settings** section, so if you have not migrated to Elephant Flow configuration settings, your device will lose the elephant flow configuration upon the next deployment.

The following table shows the IAB or elephant flow configurations that can be applied to version 7.2.0 or later and to version 7.1.0 or earlier that are running Snort 3 or Snort 2 engines.

Management Center	Threat Defense	Elephant Flow or IAB Configuration
Management Center 7.0 or 7.1	Snort 2 device	Configuration from IAB is applicable.
	Snort 3 device	Configuration from IAB is applicable.
Management Center 7.2.0	Snort 2 device	Configuration from IAB is applicable.
	Snort 3 device (7.1.0 and earlier)	Configuration from IAB is applicable.
	Snort 3 device (7.2.0 and later)	Configuration from Elephant Flow is applicable.

Configure Elephant Flow

You can configure elephant flow to take actions on elephant flows, which helps resolve issues, such as system duress, high CPU utilization, packet drops, and so on.



Attention Elephant flow detection is not applicable for prefiltered, trusted, or fast-forwarded flows, which do not process through Snort. As elephant flows are detected by Snort, elephant flow detection is not applicable for encrypted traffic.

Step 1

In the access control policy editor, click **Advanced Settings** from the **More** drop-down arrow at the end of the packet flow line. Then, click **Edit** (✎) next to **Elephant Flow Settings**.

If **View** (👁) appears instead, settings are inherited from an ancestor policy, or you do not have permission to modify the settings. If the configuration is unlocked, uncheck **Inherit from base policy** to enable editing.

Figure 1: Configure Elephant Flow Detection

Step 2 The **Elephant Flow Detection** toggle button is enabled by default. You can configure the values for flow bytes and flow duration. When they exceed your configured values, elephant flow events are generated.

Step 3 To remediate elephant flows, enable the **Elephant Flow Remediation** toggle button.

Step 4 To set the criteria for remediation of the elephant flow, configure the values for CPU utilization %, duration of fixed time windows, and packet drop %.

Step 5 You can perform the following actions for elephant flow remediation when it meets the configured criteria:

- a. **Bypass the flow**—Enable this button to bypass Snort inspection for selected applications or filters. Choose from:
 - **All applications including unidentified applications**—Select this option to bypass all the application traffic. If you configure this option, you cannot configure the throttle action (rate-limit) for any flow.
 - **Select Applications/Filters**—Select this option to select the applications or filters whose traffic you want to bypass; see the topic **Configuring Application Conditions and Filters** in the **Access Control Rules** chapter in the [Cisco Secure Firewall Management Center Device Configuration Guide](#).
- b. **Throttle the flow**—Enable this button to apply rate-limit to the flow and continue to inspect flows. Note that you can select the applications or filters to bypass Snort inspection and throttle the remaining flows.

Note Automatic removal of throttle from a throttled elephant flow occurs when the system is out of duress, that is, the percentage of Snort packet drops is lesser than your configured threshold. Consequently, rate limiting is also removed.

You can also manually remove throttling from a throttled elephant flow, using the following threat defense commands:

- **clear efd-throttle <5-tuple/all> bypass**—This command removes throttling from the throttled elephant flow and bypasses Snort inspection.
- **clear efd-throttle <5-tuple/all>**—This command removes throttling from the throttled elephant flow and Snort inspection continues. Elephant flow remediation is skipped after using this command.

For more information about these commands, see the [Cisco Secure Firewall Threat Defense Command Reference](#).

Note Taking action on elephant flows (bypass and throttle the flow) is not supported on Cisco Firepower 2100 series devices.

Step 6 In the **Remediation Exemption Rule** section, click **Add Rule** to configure L4 access control list (ACL) rules for flows that must be exempted from remediation.

Step 7 In the **Add Rule** window, use the **Networks** tab to add the network details, that is the source network and the destination network. Use the **Ports** tab to add the source port and the destination port.

If an elephant flow is detected and it matches the rules that are defined, an event is generated with the reason as **Elephant Flow Exempted** in the **Reason** column header of **Connection Events**.

Step 8 In the **Remediation Exemption Rule** section, you can view the flows that are exempt from the remediation action.

Step 9 Click **OK** to save the elephant flow settings.

Step 10 Click **Save** to save the policy.

What to do next

Deploy configuration changes; see [Deploy Configuration Changes](#).

After configuring your elephant flow settings, monitor your connection events to see if any flows are detected, bypassed, or throttled. You can view this in the **Reason** field of your connection event. The three reasons for elephant flow connections are:

- Elephant Flow
- Elephant Flow Throttled
- Elephant Flow Trusted



Attention Enabling elephant flow detection alone does not cause generation of connection events for elephant flows. If a connection event is already logged for another reason and the flow is also an elephant flow, then the **Reason** field contains this information. However, to ensure that you are logging all elephant flows, you must enable connection logging in the applicable access control rules.

Refer to [Cisco Secure Firewall Elephant Flow Detection](#) for more information.



PART **V**

Snort 3 Use Cases

- [Migrate from Snort 2 to Snort 3 In Secure Firewall Management Center, on page 111](#)
- [Generate Snort 3 Recommendations In Secure Firewall Management Center, on page 121](#)
- [Block Traffic Based on the EVE Threat Confidence Score, on page 129](#)
- [Configure Elephant Flow Detection Outcomes, on page 135](#)
- [Mitigate Threats Using MITRE Framework in Snort 3 Intrusion Policies, on page 145](#)



CHAPTER 9

Migrate from Snort 2 to Snort 3 In Secure Firewall Management Center

- [Migrate from Snort 2 to Snort 3, on page 111](#)
- [Benefits of Migrating to Snort 3, on page 111](#)
- [Sample Business Scenario, on page 112](#)
- [Best Practices for Migrating from Snort 2 to Snort 3, on page 112](#)
- [Prerequisites, on page 112](#)
- [End-to-End Migration Workflow, on page 112](#)
- [Enable Snort 3 on Threat Defense, on page 113](#)
- [Convert Snort 2 Rules of a Single Intrusion Policy to Snort 3, on page 114](#)
- [Deploy Configuration Changes, on page 119](#)

Migrate from Snort 2 to Snort 3

Snort is an intrusion detection and prevention system that has undergone a significant change from Version 2 to Version 3. To leverage the enhanced features and capabilities of Snort 3, migration of the existing rule sets from Snort 2 becomes crucial. This migration process involves converting and adapting the Snort 2 rules to the Snort 3 rule syntax and optimizing them for improved detection and performance.

In some cases, organizations can have the threat defense devices managed by the Secure Firewall Management Center. Organizations can opt for a hybrid deployment approach during the migration from Snort 2 to Snort 3. This approach allows for a gradual transition and minimizes potential disruptions, if any.

Benefits of Migrating to Snort 3

- **Enhanced protocol support**—Snort 3 provides improved protocol support, allowing you to monitor and detect threats across a wide range of modern protocols, including encrypted traffic.
- **Streamlined rule management**—Snort 3 offers a more user-friendly rule language and rule management system, making it easier to create, modify, and manage rules effectively.
- **Improved performance**—Snort 3 has been optimized to handle higher traffic volumes more efficiently, reducing the risk of performance bottlenecks and ensuring timely threat detection.

Sample Business Scenario

Alice works as a security analyst in a large organization that heavily relies on the Snort inspection engine to monitor and protect their network infrastructure. The organization has been using Snort Version 2 for several years, but they have encountered some limitations and challenges.

Bob, the network administrator, is looking to migrate from Snort 2 to Snort 3 to overcome these issues and enhance his organization's network security capabilities.

This migration will also improve network security monitoring, enhance performance, and streamline rule management.

Best Practices for Migrating from Snort 2 to Snort 3


- Back up your intrusion policy before performing the migration. See the Export Configurations task in the [Cisco Secure Firewall Management Center Administration Guide](#).
- Before upgrading a device to Snort 3, if changes are made in Snort 2, use the synchronize utility to include the latest synchronization from Snort 2 to Snort 3 so that you can start with a similar coverage. See [Synchronize Snort 2 Rules with Snort 3](#), on page 22.
- Snort 2 custom rules are not automatically converted to Snort 3 and must be manually migrated. See [Convert Snort 2 Custom IPS Rules to Snort 3](#), on page 20.
- Synchronization does not migrate Snort 2 rules with thresholds or suppressions. These rules must be created again in Snort 3.

Prerequisites

- Have a working knowledge of Snort. To learn about the Snort 3 architecture, see [Snort 3 Adoption](#).
- Back up your management center. See [Backup the Management Center](#).
- Back up your intrusion policy. See [Exporting Configurations](#).

End-to-End Migration Workflow

The following flowchart illustrates the workflow for migrating Snort 2 to Snort 3 in Secure Firewall Management Center.



Step	Description
1	Enable Snort 3 on the device. See Enable Snort 3 on Threat Defense, on page 113 .
2	Convert Snort 2 rules to Snort 3. See Convert Snort 2 Rules of a Single Intrusion Policy to Snort 3, on page 114 .
3	Deploy configuration. See Deploy Configuration Changes, on page 23 .

Enable Snort 3 on Threat Defense



Attention During the deployment process, there could be a momentary traffic loss because the current inspection engine needs to be shut down.

- Step 1** Choose **Devices > Device Management**.
- Step 2** Click the corresponding device to go to the device home page.
- Step 3** Click the **Device** tab.
- Step 4** In the **Inspection Engine** section, click **Upgrade**.

Inspection Engine

Inspection Engine: Snort 2

Before you upgrade, read and understand the Snort 3 configuration guide for your version: <https://www.cisco.com/go/fmc-snort3>. Pay special attention to feature limitations and migration instructions. Although upgrading to Snort 3 is designed for minimal impact, features do not map exactly. Custom intrusion rules are not automatically migrated during upgrade but [options](#) are available to migrate. Careful planning and preparation can help you make sure that traffic is handled as expected.

Upgrading to Snort 3 also deploys configuration changes to affected devices. This briefly interrupts traffic flow and inspection on all devices, including those configured for high availability/scalability. Interface configurations determine whether traffic drops or passes without inspection during the interruption. For details, see the [Snort Restart Traffic Behavior](#) section in the online help.

Upgrade to Snort3 should be done during a maintenance window.

Upgrade

Step 5 Click **Yes**.

What to do next

Deploy the changes on the device. See [Deploy Configuration Changes, on page 23](#).

The system converts your policy configurations during the deployment process to make them compatible with the selected Snort version.

Convert Snort 2 Rules of a Single Intrusion Policy to Snort 3

Step 1 Choose **Policies > Intrusion**.

Step 2 In the **Intrusion Policies** tab, click **Show Snort 3 Sync status**.

Firewall Management Center Overview


Policies / Access Control / Intrusion / [Intrusion Policies](#)

Intrusion Policies Network Analysis Policies

Show Snort 3 Sync status 🔍 Search by Intrusion Policy, Description, or Bas

Intrusion Policy	Description
_Intrusion_Policy_1	

If your policy displays an orange arrow, it indicates that the Snort 2 and the Snort 3 versions of the intrusion policy are not synchronized.

Intrusion Policy	Description
_Intrusion_Policy_1	 Snort 3 is out of sync with Snort 2. 2023-07-

Step 3

Click the orange arrow.

The **Snort 2 to Snort 3 Sync Summary** page displays that the Snort 2 to Snort 3 sync is pending.

Snort 2 to Snort 3 Sync Summary ?


This is a utility to synchronize Snort 2 policy configuration with Snort 3 version to start with a similar coverage.

- Snort 3 policy configuration is synched from Snort 2 version by the system when Firewall Management Center is upgraded from pre-7.0 version.
- Before upgrading a device to Snort 3, If changes are made in Snort 2 version, you can use this utility to have the latest synchronization from Snort 2 version to Snort 3 version so that you start with similar coverage.

Note: After moving to Snort 3, it is recommended that you manage the Snort 3 version of the policy independently and do not use this utility as a regular operation.

[Click here](#) to learn more.

Policy Name:

 **Snort 3 and Snort 2 Sync Pending** 2023-07-09 21:16:51 EDT

Used by: 1 Access Control Policy | 1 Device

Step 4

Click **Re-Sync** to start the synchronization.

Note When you click **Re-Sync**, the snort2Lua tool converts the rules from Snort 2 to Snort 3.

The **Summary Details** section lists the rules that were migrated or skipped. In our use case, there are 76 custom Snort 2 rules, 17 rules with thresholds, and 15 rules with suppression that were skipped during the sync process. To migrate the custom rules, go to the next step.

Convert Snort 2 Rules of a Single Intrusion Policy to Snort 3

Policy Name: **_Intrusion_Policy_1**

➔ Snort 3 is partially in sync with Snort 2. 2023-08-01 05:42:52 EDT

Used by: 1 Access Control Policy | 0 Devices (Snort 2), 1 Devices (Snort 3)

Summary Details

Rule Overrides

- Based on Talos rule-mapping 18639 Snort 2 rule action overrides migrated to 18635 Snort 3 rules.
- ▲ Rules migration skipped for 17 rules with threshold, 15 rules with suppression, as sync of Suppression and Threshold setting(s) are not supported.

▲ Rules migration skipped for 76 custom rules, as sync of Custom Rule setting(s) are not supported. You can manually convert the Snort 2 custom rules to Snort 3 using the snort2Lua tool.

Download Summary Details

Overridden Advanced **Custom Rules**

The custom rules are not auto-converted to the Snort 3 version, as Snort 3 rules are written differently compared to Snort 2 rules. Use one of the following options to convert the custom rules manually:

To migrate rules with thresholds and suppressions, go to [Step 6](#).

Policy Name: **_Intrusion_Policy_1**

➔ Snort 3 is partially in sync with Snort 2. 2023-08-01 05:42:52 EDT

Used by: 1 Access Control Policy | 0 Devices (Snort 2), 1 Devices (Snort 3)

Summary Details

Rule Overrides

- Based on Talos rule-mapping 18639 Snort 2 rule action overrides migrated to 18635 Snort 3 rules.

▲ Rules migration skipped for 17 rules with threshold, 15 rules with suppression, as sync of Suppression and Threshold setting(s) are not supported.

▲ Rules migration skipped for 76 custom rules, as sync of Custom Rule setting(s) are not supported. You can manually convert the Snort 2 custom rules to Snort 3 using the snort2Lua tool.

Download Summary Details


Overridden Advanced **Custom Rules**

The custom rules are not auto-converted to the Snort 3 version, as Snort 3 rules are written differently compared to Snort 2 rules. Use one of the following options to convert the custom rules manually:

Step 5


To migrate the 76 custom rules, perform either one of these steps:

- In the **Custom Rules** tab, click the **Import** icon to convert and auto-import the local rules to the Snort 3 version of the policy.




A confirmation message is displayed after the rules are successfully imported.


- Choose **Objects > Intrusion Rules** and click **Snort 3 All Rules**.
 - a. Click **Local Rules** in the left panel to check if any rules have been migrated. Notice that no custom rules from Snort 2 have been migrated.
 - b. From the **Tasks** drop-down list, choose **Convert Snort 2 rules and import**.



c. Click **OK**.



A newly created rule group (**All Snort 2 Converted Global**) is created under **Local Rules** in the left panel. Notice that all 76 custom rules have been migrated, as shown in the following figure.



Alternatively, you can select the **Convert Snort 2 rules and download** in the previous step to save the rules file locally. You can review the converted rules in the downloaded file and later upload them using the **Upload Snort 3 rules** option.

Step 6 Click the **Download Summary Details** link to download the rules in .txt format.

The following is a sample of the summary that is displayed.

```
"id": "00505691-15DC-0ed3-0000-004294988561",
"name": "_Intrusion_Policy_1",
"type": "IntrusionPolicy",
"syncStatus": {
  "source": {
    "id": "bdce2d6a-1ebe-11ee-8e88-220032eb1fb5",
    "type": "IntrusionPolicy"
  },
  "status": "WARN",
  "description": "Migration is partially successful. Some of the rules are not copied to Snort3.",
  "timestamp": 1690883954814,
  "lastUser": {
```

```

    "name": "admin"
  },
  "details": [
    {
      "type": "Summary",
      "status": "INFO",
      "description": "Based on Talos rule-mapping 18639 Snort 2 rule action overrides migrated
to 18635 Snort 3 rules."
    },
    {
      "id":
"1:1000156=alert,1:1000114=alert,1:1000160=alert,1:1000135=alert,1:1000115=alert,1:1000118=alert,
1:1000092=alert,1:1000139=alert,1:1000123=alert,1:1000159=alert,1:1000149=disabled,1:1000167=alert,

1:1000133=alert,1:1000095=alert,1:1000143=alert,1:1000106=alert,1:1000153=alert,1:1000097=alert,1:1000141=alert,

1:1000148=alert,1:1000090=alert,1:1000119=alert,1:1000112=alert,1:1000138=alert,1:1000128=alert,1:1000132=alert,

1:1000134=alert,1:1000145=disabled,1:1000110=disabled,1:1000107=alert,1:1000163=alert,1:1000124=alert,1:1000125=alert,

1:1000094=alert,1:1000113=disabled,1:1000147=alert,1:1000161=alert,1:1000105=disabled,1:1000140=alert,1:1000111=alert,

1:1000102=alert,1:1000129=disabled,1:1000108=alert,1:1000144=disabled,1:1000088=alert,1:1000091=alert,1:1000131=alert,

1:1000157=alert,1:1000120=alert,1:1000126=alert,1:1000165=alert,1:1000146=alert,1:1000162=alert,1:1000116=alert,1:1000142=alert,

1:1000170=disabled,1:1000169=alert,1:1000104=alert,1:1000099=disabled,1:1000171=alert,1:1000093=alert,1:1000087=alert,1:1000100=alert,

1:1000137=alert,1:1000158=alert,1:1000103=alert,1:1000098=alert,1:1000127=disabled,1:1000130=alert,1:1000164=alert,1:1000089=alert,

1:1000109=alert,1:1000136=alert,1:1000117=alert,1:1000166=alert,1:1000168=alert",
      "type": "PolicyInfo",
      "description": "Corresponding Snort 2 policy overridden custom (local) rules."
    },
    {
      "type": "AssignedDevices",
      "status": "INFO",
      "description": "Snort3:0 , Snort2:0"
    },
    {
      "id": "122:6",
      "type": "Threshold",
      "status": "ERROR",
      "description": "PSNG_TCP_FILTERED_DECOY_PORTSCAN"
    },
    {
      "id": "122:15",
      "type": "Threshold",
      "status": "ERROR",
      "description": "PSNG_IP_PORTSWEEP_FILTERED"
    },
    {
      "id": "122:1",
      "type": "Threshold",
      "status": "ERROR",

```

```

    "description": "PSNG_TCP_PORTSCAN"
  },

```

- Step 7** Click **Close** to close the **Sync Summary** dialog box.
- Step 8** To check the rules with status: ERROR, choose **Policies > Intrusion** and click the **Snort 2** version of the intrusion policy.
- Step 9** Under **Policy Information**, click **Rules** and filter for the rule. For example, enter **PSNG_TCP_PORTSCAN** in the **Filter** field to find the rule.
- Step 10** Click **Show Details** to view the detailed version of the rule.
- Step 11** Create the rule again in Snort 3 using Snort 3 rule guidelines and save the file as a .txt or .rules file. For more information, see www.snort3.org.
- Step 12** Upload the custom rule that you just created locally to the list of all the Snort 3 rules. See [Add Custom Rules to Rule Groups](#).

What to do next

Deploy configuration changes. See [Deploy Configuration Changes, on page 23](#).

Deploy Configuration Changes

After you change configurations, deploy them to the affected devices.



Note This topic covers the basic steps involved in deploying configuration changes. We *strongly* recommend that you refer the *Deploy Configuration Changes* topic in the latest version of the *Cisco Secure Firewall Management Center Configuration Guide* to understand the prerequisites and implications of deploying the changes before proceeding with the steps.



Caution When you deploy, resource demands may result in a small number of packets dropping without inspection. Additionally, deploying some configurations restarts the Snort process, which interrupts traffic inspection. Whether traffic drops during this interruption or passes without further inspection depends on how the target device handles traffic.

- Step 1** On the Secure Firewall Management Center menu bar, click **Deploy** and choose **Deployment**.

The GUI page lists the devices with out-of-date configurations having **Pending** status.

- The **Modified By** column lists the users who have modified the policies or objects. Expand the device listing to view the users who have modified the policies for each policy listing.


Note Usernames are not provided for deleted policies and objects.


- The **Inspect Interruption** column indicates if traffic inspection interruption might occur in the device during deployment.


If this column is blank for a device, it indicates that there will be no traffic inspection interruptions on that device during deployment.

- The **Last Modified Time** column specifies the last time you made configuration changes.
- The **Preview** column allows you to preview the changes for the next deployment.
- The **Status** column provides the status for each deployment.

Step 2 Identify and choose the devices on which you want to deploy configuration changes.

- Search—Search for the device name, type, domain, group, or status in the search box.
- Expand—Click **Expand Arrow** () to view device-specific configuration changes to be deployed.

When you check a check box adjacent to a device, all the changes made to the device and listed under the device, are pushed for deployment. However, you can use **Policy selection** () to select individual policies or specific configurations to deploy while withholding the remaining changes without deploying them.

- Note**
- When the status in the **Inspect Interruption** column indicates (**Yes**) that deploying will interrupt inspection, and perhaps traffic, on a threat defense device, the expanded list indicates the specific configurations causing the interruption with the **Inspect Interruption** ().
 - When there are changes to interface groups, security zones, or objects, the impacted devices are shown as out-of-date on the management center. To ensure that these changes take effect, the policies with these interface groups, security zones, or objects, also need to be deployed along with these changes. The impacted policies are shown as out-of-date on the **Preview** page on the management center.

Step 3 Click **Deploy**.

Step 4 If the system identifies errors or warnings in the changes to be deployed, it displays them in the **Validation Messages** window. To view complete details, click the arrow icon before the warnings or errors.

You have the following choices:

- Deploy—Continue deploying without resolving warning conditions. You cannot proceed if the system identifies errors.
- Close—Exit without deploying. Resolve the error and warning conditions, and attempt to deploy the configuration again.

What to do next

During deployment, if there is a deployment failure, there is a possibility that the failure may impact traffic. However, it depends on certain conditions. If there are specific configuration changes in the deployment, the deployment failure may lead to traffic being interrupted. For details, see the Deploy Configuration Changes topic in the latest version of the *Cisco Secure Firewall Management Center Configuration Guide*.



CHAPTER 10

Generate Snort 3 Recommendations In Secure Firewall Management Center

- [Snort 3 Rule Recommendations, on page 121](#)
- [Benefits, on page 122](#)
- [Sample Business Scenario, on page 122](#)
- [Best Practices, on page 122](#)
- [Prerequisites, on page 122](#)
- [Generate Snort 3 Recommendations, on page 122](#)
- [Deploy Configuration Changes, on page 125](#)

Snort 3 Rule Recommendations

Rule recommendations automatically tune your intrusion policy with rules that are specific to the host environment. You can enable additional rules or tune the current rule set by disabling rules for the vulnerabilities that are not present in your network. For more information, see [Overview of Secure Firewall Recommended Rules, on page 55](#).

How does it work?

The management center builds a database of hosts on your network with details such as the IP address, hostname, operating system, services, users, and client applications through passive discovery. Based on this information, the system maps vulnerabilities to each discovered host. The Recommendations feature uses this host database to determine the rules that apply to your environment.

In Snort 3, there are four security levels, each corresponding to a specific Talos policy. They are:

- Level 1—Connectivity Over Security
- Level 2—Balanced Security and Connectivity
- Level 3—Security Over Connectivity
- Level 4—Maximum Detection

Check the **Accept Recommendations to Disable Rules** check box to disable rules for vulnerabilities not found on the hosts in your network. Check this option only if you have to trim your rule set because of a high number of alerts, or to improve inspection performance.

Benefits

- By configuring recommendations, you can tailor your intrusion policy to detect specific types of threats more effectively using rules that are specific to the host environment.
- Recommendations contribute to a more efficient and effective incident response process by reducing false positives and false negatives.

Sample Business Scenario

A large corporate network uses Snort 3 as its primary intrusion detection and prevention system. In a rapidly evolving threat landscape, robust network security measures must be adopted. The security team wants to enhance their incident response capabilities. One of the ways to do that is to generate recommendations or rule sets based on the vulnerabilities detected in the host network. This helps to optimize their intrusion policies, thereby safeguarding the network more effectively.

Best Practices


- You must have quality accurate host data.
Because of the passive nature of Network Discovery, your threat defense devices must be positioned as close as possible to your protected hosts. This allows the threat defense devices to watch network traffic to and from these hosts, giving you an accurate data about applications, services, and vulnerabilities present on your network.
- Devices should have visibility to East-West as well as North-South traffic flows to build an accurate host profile.
- You can create a scheduled task to update recommendations automatically.

Prerequisites


- Ensure that hosts are present in the system to generate recommendations.
- Protected networks configured for recommendations should map to the hosts present in the system.

Generate Snort 3 Recommendations

-
- Step 1** Choose **Policies > Intrusion**.
 - Step 2** Click the **Snort 3 Version** button of the corresponding intrusion policy.
 - Step 3** Click the **Recommendations (Not in Use)** layer to configure the rule recommendations.



In the **Cisco Recommended Rules** window, you can set the security level.



Step 4 Click to select the security level.

Step 5 (Optional) Check the **Accept Recommendation to Disable Rules** check box to disable the rules written for vulnerabilities not found on the hosts in your network.

Use this option, only if you have to trim your rule set because of a high number of alerts or to improve inspection performance.

Step 6 From the **Protected Networks** drop-down list, choose the network objects that must be examined by the recommendations. By default, any IPv4 or IPv6 networks are selected if you do not make a selection.

Click **Add +** to create a new network object of type **Host** or **Network** and click **Save**.


Step 7 Generate and apply recommendations:

- **Generate**—Generates the recommendations for an intrusion policy. This action lists the rules under **Recommended Rules (Not in use)**.
- **Generate and Apply**—Generates and applies the recommendations for an intrusion policy. This action lists the rules under **Recommended Rules (Not in use)**.


Recommendations are generated successfully. A new recommendation tab appears with all the recommended rules and their corresponding recommended actions. Rule action preset filters are also available for this tab, in addition to new recommendations.

Step 8 Verify the recommendations and then apply them accordingly:

- **Accept**—Applies the previously generated recommendations for an intrusion policy.
- **Refresh**—Regenerates and updates the rule recommendations for an intrusion policy.
- **Edit**—Opens the **Recommendations** dialog box where you can provide the recommendation input values and then generate the recommendations.
- **Discard**—Either reverts or removes the applied recommended rules from the policy; also removes the **Recommendations** tab.



Under **All Rules**, the Recommended Rules section displays the recommended rules.



Step 9 To effectively use recommendations, they must be updated periodically. Follow these steps:

- Choose **System >Tools >Scheduling**.
- Click **Add Task**.
- Choose **Cisco Recommended Rules** from the **Job Type** drop-down list.
- Update the required fields, as needed.

New Task

Job Type (Cisco Recommended Rules must first be configured in the selected policies)

Schedule task to run Once Recurring

Start On America/New York

Repeat Every Hours Days Weeks Months

Run At

Repeat On Sunday Monday Tuesday Wednesday Thursday Friday Saturday

Job Name

Policies All Policies

_Intrusion_Policy_1

e. Click **Save**.

What to do next

Deploy configuration changes. See [Deploy Configuration Changes, on page 23](#).

Deploy Configuration Changes

After you change configurations, deploy them to the affected devices.



Note This topic covers the basic steps involved in deploying configuration changes. We *strongly* recommend that you refer the *Deploy Configuration Changes* topic in the latest version of the *Cisco Secure Firewall Management Center Configuration Guide* to understand the prerequisites and implications of deploying the changes before proceeding with the steps.



Caution When you deploy, resource demands may result in a small number of packets dropping without inspection. Additionally, deploying some configurations restarts the Snort process, which interrupts traffic inspection. Whether traffic drops during this interruption or passes without further inspection depends on how the target device handles traffic.

Step 1 On the Secure Firewall Management Center menu bar, click **Deploy** and choose **Deployment**.

The GUI page lists the devices with out-of-date configurations having **Pending** status.

- The **Modified By** column lists the users who have modified the policies or objects. Expand the device listing to view the users who have modified the policies for each policy listing.


Note Usernames are not provided for deleted policies and objects.


- The **Inspect Interruption** column indicates if traffic inspection interruption might occur in the device during deployment.


If this column is blank for a device, it indicates that there will be no traffic inspection interruptions on that device during deployment.

- The **Last Modified Time** column specifies the last time you made configuration changes.
- The **Preview** column allows you to preview the changes for the next deployment.
- The **Status** column provides the status for each deployment.

Step 2 Identify and choose the devices on which you want to deploy configuration changes.

- Search—Search for the device name, type, domain, group, or status in the search box.
- Expand—Click **Expand Arrow** () to view device-specific configuration changes to be deployed.

When you check a check box adjacent to a device, all the changes made to the device and listed under the device, are pushed for deployment. However, you can use **Policy selection** () to select individual policies or specific configurations to deploy while withholding the remaining changes without deploying them.

- Note**
- When the status in the **Inspect Interruption** column indicates (**Yes**) that deploying will interrupt inspection, and perhaps traffic, on a threat defense device, the expanded list indicates the specific configurations causing the interruption with the **Inspect Interruption** ().
 - When there are changes to interface groups, security zones, or objects, the impacted devices are shown as out-of-date on the management center. To ensure that these changes take effect, the policies with these interface groups, security zones, or objects, also need to be deployed along with these changes. The impacted policies are shown as out-of-date on the **Preview** page on the management center.

Step 3 Click **Deploy**.

Step 4 If the system identifies errors or warnings in the changes to be deployed, it displays them in the **Validation Messages** window. To view complete details, click the arrow icon before the warnings or errors.

You have the following choices:

- Deploy—Continue deploying without resolving warning conditions. You cannot proceed if the system identifies errors.
- Close—Exit without deploying. Resolve the error and warning conditions, and attempt to deploy the configuration again.

What to do next

During deployment, if there is a deployment failure, there is a possibility that the failure may impact traffic. However, it depends on certain conditions. If there are specific configuration changes in the deployment, the deployment failure may lead to traffic being interrupted. For details, see the Deploy Configuration Changes topic in the latest version of the *Cisco Secure Firewall Management Center Configuration Guide*.



CHAPTER 11

Block Traffic Based on the EVE Threat Confidence Score

- [About Encrypted Visibility Engine, on page 129](#)
- [Benefits, on page 129](#)
- [Sample Business Scenario, on page 129](#)
- [Prerequisites, on page 130](#)
- [High-Level Workflow, on page 130](#)
- [Configure Block Thresholds in EVE, on page 130](#)
- [Additional References, on page 134](#)

About Encrypted Visibility Engine

You can use the Encrypted Visibility Engine (EVE) to identify client applications and processes using Transport Layer Security (TLS) encryption. EVE provides more visibility into the encrypted sessions without decryption. Based on EVE's findings, administrators can enforce policy actions on the traffic within their environments. You can also use the EVE to identify and stop malware.

Benefits

Administrators can leverage and adjust EVE's threat score to block malicious encrypted traffic. If the probability that the incoming traffic is malicious, then based on the threat score, you can configure EVE to block the connection.

Sample Business Scenario

A large corporate network uses Snort 3 as its primary intrusion detection and prevention system. In a rapidly evolving threat landscape, adoption of robust network security measures is necessary and important. The security team uses EVE to enhance encrypted traffic inspection without the need to implement full man-in-the-middle (MITM) decryption. The EVE technology uses fingerprints of known malicious processes to identify and stop malware. Network administrators must have the flexibility to configure EVE's block traffic thresholds to block potentially malicious connections, which are based on their configured block thresholds.

Prerequisites

- You must be running management center 7.4.0 or later, and the managed threat defense must also be 7.4.0 or later.
- Ensure that you have a valid Intrusion Prevention System (IPS) license and Snort 3 is the detection engine.


High-Level Workflow

1. EVE analyzes the incoming traffic and gives a verdict on the probability of incoming traffic being malware or not.
2. If EVE detects incoming traffic to be malware with a certain level of confidence, you can configure EVE to block that traffic.
3. The packets are first checked for malware probability or threat score, and the threat score is compared with the block threshold that you have set.
4. If the threat score is higher than the configured threshold, EVE blocks the traffic.
5. If the threat score is lesser than the configured threshold, EVE takes no action.

Configure Block Thresholds in EVE

This procedure shows how to block potentially malicious traffic, based on the EVE threat confidence score of 90 percent or higher.

-
- Step 1** Choose **Policies > Access Control**.
- Step 2** Click **Edit** (✎) next to the access control policy you want to edit.
- Step 3** Choose **Advanced Settings** from the **More** drop-down arrow at the end of the packet flow line.
- Step 4** Click **Edit** (✎) next to **Encrypted Visibility Engine**.



Step 5
Step 6

In the **Encrypted Visibility Engine** page, enable the **Encrypted Visibility Engine (EVE)** toggle button.
Enable the **Block Traffic Based on EVE Score** toggle button. Any incoming traffic that is a potential threat is blocked by default.

Encrypted Visibility Engine

About Encrypted Visibility Engine

This encrypted visibility engine (EVE) uses machine learning to provide insights into the encrypted sessions without decrypting them. To use this feature, you require a valid IPS license and feature support is only for Snort 3 devices. [Learn more](#)

Recommended Settings

- [Enable](#) automatic updates for future Cisco Vulnerability Database (VDB) releases.
- [Enable](#) Cisco Success Network.

Encrypted Visibility Engine (EVE)



Use EVE for Application Detection



Allow EVE to assign client applications to processes.

Block Traffic Based on EVE Score



Customize your threshold for blocking traffic based on the EVE scores.

Advanced Mode



Block



Revert to Defaults

Cancel

OK

- Note** By default, the threshold at which malware is blocked is 99 percent, which means:
- If EVE detects the traffic to be malware with 99 percent confidence or higher, EVE blocks the traffic.
 - If EVE detects the traffic to be malware with less than 99 percent confidence, EVE takes no action.

Step 7 Use the slider to adjust the threshold for blocking based on EVE threat confidence. This ranges from **Very Low** to **Very High**. In this example, the slider is set to **Very High**.

Encrypted Visibility Engine ?

About Encrypted Visibility Engine

This encrypted visibility engine (EVE) uses machine learning to provide insights into the encrypted sessions without decrypting them. To use this feature, you require a valid IPS license and feature support is only for Snort 3 devices. [Learn more](#)

Recommended Settings ∨

- [Enable](#) automatic updates for future Cisco Vulnerability Database (VDB) releases.
- [Enable](#) Cisco Success Network.

Encrypted Visibility Engine (EVE)

Use EVE for Application Detection

Allow EVE to assign client applications to processes.

Block Traffic Based on EVE Score

i Customize your threshold for blocking traffic based on the EVE scores.

i **Advanced Mode**

— Block


Very Low Low Medium High Very High

Revert to Defaults
Cancel
OK

Step 8 For further granular control, enable the **Advanced Mode** toggle button. Now, you can assign a specific EVE Threat Confidence Score for blocking traffic. The default threshold is 99 percent.

Step 9 In this example, change the block threshold to **90** percent.

Attention As a best practice, we recommend that you do not set the block threshold to below 50 percent to ensure optimum performance.



Step 10 Click **OK**.

Step 11 Click **Save**.

What to do next

Deploy configuration changes. See [Deploy Configuration Changes, on page 23](#).

View EVE Events

Step 1 To verify the block action, choose **Analysis > Connections > Events**. You can also view the events from the **Unified Events** viewer.

Step 2 If you have configured EVE to block traffic, the **Reason** field shows **Encrypted Visibility Block**.

Q Source IP 172.16.77.1 X Select...

Showing all 10 events (↔ 10) ↓

	Time	Action	Reason
>	2023-01-10 14:22:33	Block	Encrypted Visibility Block
>	2023-01-10 14:22:28	Block	Encrypted Visibility Block
>	2023-01-10 14:22:25	Block	Encrypted Visibility Block
>	2023-01-10 14:14:13	Block	Encrypted Visibility Block
>	2023-01-10 14:14:10	Block	Encrypted Visibility Block
>	2023-01-10 14:14:06	Block	Encrypted Visibility Block
>	2023-01-10 14:12:40	Block	Encrypted Visibility Block
>	2023-01-10 14:12:40	Allow	
>	2023-01-10 14:12:34	Block	Encrypted Visibility Block
>	2023-01-10 14:12:34	Allow	

Step 3 The following is an example of the **Encrypted Visibility Process Name** as `test_malware`, **Encrypted Visibility Threat Confidence** as **Very High**, and **Encrypted Visibility Threat Confidence Score** as **90** percent.

Q Source IP 172.16.77.1 X Select... Refresh

Showing all 10 events (↔ 10) ↓ 2023-01-10 13:25:02 EST → 2023-01-10 14:25:02 EST 1h Go Live

Time	Application	URL	Encrypted Visibility Fingerprint	Encrypted Visibility Process Confidence Score	Encrypted Visibility Process Name	Encrypted Visibility Threat Confidence	Encrypted Visibility Threat Confidence Score
2023-01-10 14:22:33			tls/(0303)(130213031:	90%	test_malware	Very High	90%
2023-01-10 14:22:28			tls/(0303)(130213031:	90%	test_malware	Very High	90%
2023-01-10 14:22:25			tls/(0303)(130213031:	90%	test_malware	Very High	90%
2023-01-10 14:14:13			tls/(0303)(130213031:	90%	test_malware	Very High	90%

Additional References

For detailed conceptual information, see the Encrypted Visibility Engine for Snort 3 chapter in this guide or the content in the following link:

[Encrypted Visibility Engine](#)



CHAPTER 12

Configure Elephant Flow Detection Outcomes

- [About Elephant Flows, on page 135](#)
- [Benefits of Elephant Flow Detection and Remediation, on page 135](#)
- [Elephant Flow Workflow, on page 135](#)
- [Sample Business Scenario, on page 136](#)
- [Prerequisites, on page 136](#)
- [Configure Elephant Flow Parameters, on page 137](#)
- [Configure Elephant Flow Remediation Exemption, on page 140](#)
- [Additional References, on page 143](#)

About Elephant Flows

Elephant flows are extremely large (in total bytes), relative long-running network connections set up by a TCP (or other protocols) flow measured over a network link. By default, elephant flows are flows or connections that are larger than 1 GB per 10 seconds. They can cause performance duress or issues in Snort cores. Elephant flows are important because they can potentially consume an excessive amount of CPU resources and impact other competing flows for detection resources and cause issues, such as increased latency or packet drops.

Benefits of Elephant Flow Detection and Remediation

- Elephant flow configuration allows customization and the option to bypass or even throttle elephant flows.
- You can choose to bypass or throttle flows that are based on your chosen applications to provide Snort inspection of suspect traffic, while bypassing more trusted traffic.
- Elephant flow remediation helps prioritize and free up more bandwidth for your internal applications, depending on your specific requirements.


Elephant Flow Workflow

When an elephant flow is detected based on your configured parameters, you can choose to bypass or throttle the flow. When a flow is bypassed, the traffic is allowed to pass without Snort inspection. Throttling indicates that the flow throughput is reduced. The reduction on flow rate is done in 10 percent increments until the CPU

utilization reduces to below the configured threshold. Bypassing or throttling happens after identifying the elephant flow and meeting the additional CPU and time window parameters. Prior to identification of the elephant flow, your intrusion policy processes the flow, assuming that you have configured this in an Allow rule. This means that elephant flows are not allowed to pass through the system completely uninspected because most of the attacks are detected very early in a connection.

To understand how flows are handled, see the following flow diagram.

Figure 2: Elephant Flow Workflow



No action is taken unless the system detects a Snort duress condition (performance issue). The system does not throttle or bypass a flow just because it is large. Also, the actions of throttle and bypass are mutually exclusive. This means that you can either bypass or throttle a flow, but not both.

If you do not want to bypass all the elephant flows causing duress, you can limit the bypass option to specific applications only. You can prioritize connectivity for the applications that you trust, without throttling performance. You can configure the applications that must be bypassed, but the remaining flows (causing duress) are throttled. This ensures that the other nontrusted application flows still receive full Snort inspection although their bandwidth is reduced.

Sample Business Scenario

In a data center, several activities are happening, such as replication of data between clusters, virtual machine integration, and database backup. Users in an organization could be watching videos on an OTT or downloading them. Bandwidth utilization for such activities might result in elephant flows, slow down the network, and impact the performance of important tasks. As a network administrator (and depending on your specific requirements), you want visibility into such large flows that are causing bandwidth issues and remediate them.

As an example, let us see how you can configure elephant flow parameters to bypass Snort inspection for WebEx traffic (which your organization uses for real-time video conferencing) and throttle the remaining applications or connections, including videos, movies, and so on.


Prerequisites

- Ensure that you are running management center 7.2.0 or later and that the managed threat defense is also 7.2.0 or later.

- Only enabling elephant flow detection does not generate additional connection events. Elephant flow detection adds the Elephant Flow notation to matching connections that are already being logged to the management center. **To log these events, you must enable connection logging in your access control policy.** You can do that for specific rules or add a Monitor rule that logs all connections, including elephant flows.


Configure Elephant Flow Parameters

- Step 1** Choose **Policies > Access Control**.
- Step 2** Click **Edit** (✎) next to the access control policy that you want to edit.
- Step 3** Choose **Advanced Settings** from the **More** drop-down arrow at the end of the packet flow line.
- Step 4** Click **Edit** (✎) next to **Elephant Flow Settings**.



- Step 5** The **Elephant Flow Detection** toggle button is enabled by default. The default setting enables detection only and no default action is configured. The detection settings allow you to adjust the flow bytes and duration so that you can identify the elephant flows in your system.

As a test setting, configure the flow bytes and duration parameters, as shown in the following figure.



- Step 6** Enable the **Elephant Flow Remediation** toggle button. When an elephant flow is detected, you can choose to bypass or throttle the flow. Bypassing a flow means that the traffic is allowed to pass without Snort inspection. Throttling

indicates that the flow throughput is reduced. This rate reduction is done in 10 percent increments until the CPU utilization reduces to lesser than the configured threshold.

As a test setting, configure the elephant flow remediation parameters as shown in the following figure.

Elephant Flow Settings

For Snort 3 FTD devices 7.2.0 onwards, use this window to configure elephant flow.
For all Snort 2 FTD devices or Snort 3 FTD devices 7.1.0 and earlier, use the Intelligent Application Bypass settings.

Elephant flow detection does not apply to encrypted traffic. [Learn more](#)

Elephant Flow Detection

Generate elephant flow events when flow bytes **exceeds** MB and flow duration **exceeds** seconds

Elephant flow Remediation ⓘ

If CPU utilization **exceeds** % in fixed time windows of seconds and packet drop **exceeds** %

Then Bypass the flow

Or Throttle the flow

Step 7 Enable the **Bypass the flow** toggle button and click the **Select Applications/Filters** radio button.

Elephant Flow Settings

For Snort 3 FTD devices 7.2.0 onwards, use this window to configure elephant flow.
For all Snort 2 FTD devices or Snort 3 FTD devices 7.1.0 and earlier, use the Intelligent Application Bypass settings.

Elephant flow detection does not apply to encrypted traffic. [Learn more](#)

Elephant Flow Detection

Generate elephant flow events when flow bytes **exceeds** MB and flow duration **exceeds** seconds

Elephant flow Remediation ⓘ

If CPU utilization **exceeds** % in fixed time windows of seconds and packet drop **exceeds** %


Then Bypass the flow

All applications including unidentified applications

Select Applications/Filters (0 selected)

Or Throttle the flow

Step 8 Under **Application Filters**, search for and select the **WebEx** application, add it to the rule, and click **Save**. This means that WebEx connections are trusted and prioritized and will skip Snort inspection if these WebEx connections are detected as elephant flows, based on the configured parameters.



- Step 9** Enable the **Throttle** toggle button to throttle the remaining flows (causing duress). This ensures that all the other flows are slowed down in 10 percent increments until the Snort duress condition is met.
- Step 10** Click **OK**.
- Step 11** Click **Save**.

What to do next


Deploy configuration changes. See [Deploy Configuration Changes](#), on page 23.

View Events for Elephant Flows


After configuring your elephant flow settings, monitor your connection events to see if any flows are detected, bypassed, or throttled. You can see this information in the **Reason** field of your connection events. The three types for elephant flow connections are:

- Elephant Flow
- Elephant Flow Throttled
- Elephant Flow Trusted

- Step 1** Choose **Analysis > Connections > Events**. You can also view the events from the **Unified Events** viewer.
- Step 2** In the **Connection Events** page, from the **Predefined Search** drop-down list, choose **Elephant Flows** to display elephant flow events.



Tip To see **Elephant Flow Trusted** or **Elephant Flow Throttled** event types, click the **Edit Search** link on the top-left corner of the page and in the **Reason** field, choose **Elephant Flows** in the left panel. Enter **Elephant Flow Trusted** or **Elephant Flow Throttled**, depending on what you want to search.



Step 3 View the elephant flow that was detected mid-flow and the **Reason** field shows **Elephant Flow**. At the end of the flow, it was bypassed and the **Reason** field shows **Elephant Flow Trusted**.

	First Packet	Last Packet	Action	Reason	Initiator IP	Initiator Country	Responder IP	Responder Country	Ingress Security Zone	Egress Security Zone	Source Port / ICMP Type
▼	2022-01-13 10:51:18	2022-01-13 10:51:46	Trust	Elephant Flow Trusted	40.1.1.20	USA	50.1.1.20	USA	inside_zone	outside_zone	37387 / tcp
▼	2022-01-13 10:51:18		Allow		40.1.1.20	USA	50.1.1.20	USA	inside_zone	outside_zone	37387 / tcp
▼	2022-01-13 10:51:18		Allow	Elephant Flow	40.1.1.20	USA	50.1.1.20	USA	inside_zone	outside_zone	37387 / tcp

Configure Elephant Flow Remediation Exemption

You can configure L4 access control list (ACL) rules for flows that must be exempted from remediation. If a flow is detected as an elephant flow and it matches the rules that are defined, that flow is exempted from the remediation action.

Before you begin

You must be running management center 7.4.0 or later and the managed threat defense must also be 7.4.0 or later.

- Step 1** Choose **Policies > Access Control**.
- Step 2** Click **Edit** (✎) next to the access control policy you want to edit.
- Step 3** Choose **Advanced Settings** from the **More** drop-down arrow at the end of the packet flow line.
- Step 4** Click **Edit** (✎) next to **Elephant Flow Settings**.

Step 5 Ensure that you have configured the elephant flow detection and remediation parameters. See [Configure Elephant Flow Parameters, on page 137](#).

Step 6 Click the **Add Rule** button next to **Remediation Exemption Rules**.

Elephant Flow Settings ?

1 For Snort 3 FTD devices 7.2.0 onwards, use this window to configure elephant flow.
For all Snort 2 FTD devices or Snort 3 FTD devices 7.1.0 and earlier, use the Intelligent Application Bypass settings.

Elephant flow detection does not apply to encrypted traffic. [Learn more](#)

Elephant Flow Detection

Generate elephant flow events when flow bytes **exceeds** MB and flow duration **exceeds** seconds

Elephant flow Remediation ?

If CPU utilization **exceeds** % in **fixed time windows of** seconds and packet drop **exceeds** %

Then Bypass the flow

All applications including unidentified applications

Select Applications/Filters (1 selected)

And Throttle the remaining flows

Remediation Exemption Rules ?

Add Rule

Serial Number	Source Networks	Destination Networks	Source Ports	Destination Ports
No Rules				

Step 7 From the list of **Available Networks**, choose the configured host to exempt from elephant flow remediation. For the purposes of this example, we have created a host called “Host1_Exception.”

Add Rule ?

Networks Ports

Search by name or value

Available Networks +

- any
- any-ipv4
- any-ipv6
- Host1_Exception
- host_exception
- IPv4-Benchmark-Tests
- IPv4-Link-Local
- IPv4-Multicast

Source Networks

any

Enter an IP address Add

Add to Source

Destination Networks

any

Enter an IP address Add

Add to Destination

Cancel Add

Step 8 Click **Add to Source** or **Add to Destination** (as required) to add this host to the source or destination.

Step 9 Click the **Ports** tab.

Step 10 For the source port, choose **Protocol** as TCP and enter **80** as the destination port, and click **Add**.

Step 11 Click **OK**.

For Snort 3 FTD devices 7.2.0 onwards, use this window to configure elephant flow.
For all Snort 2 FTD devices or Snort 3 FTD devices 7.1.0 and earlier, use the Intelligent Application Bypass settings.

Elephant flow detection does not apply to encrypted traffic. [Learn more](#)

Elephant Flow Detection

Generate elephant flow events when flow bytes **exceeds** MB and flow duration **exceeds** seconds

Elephant flow Remediation ⓘ

If CPU utilization **exceeds** % in fixed time windows of seconds and packet drop **exceeds** %

Then Bypass the flow

All applications including unidentified applications
 Select Applications/Filters (0 selected)

And Throttle the remaining flows

Remediation Exemption Rules ⓘ Add Rule

Serial Number	Source Networks	Destination Networks	Source Ports	Destination Ports
1	Host1_Exception	Host1_Exception	Any	Any

Step 12 Click **Save**.

What to do next

Deploy configuration changes. See [Deploy Configuration Changes, on page 23](#).

View Events for Elephant Flow Remediation Exemption

- Step 1** Choose **Analysis > Connections > Events**. You can also view the events from the **Unified Events** viewer.
- Step 2** View the elephant flows that were exempted from remediation. The **Reason** field shows **Elephant Flow Exempted**.

Firewall Management Center
Analysis / Connections / Events

Overview Analysis Policies Devices Objects Integration Deploy

Bookmark This Page | Reporting | Dashboard | View Bookmarks | Search

Predefined Searches

Connection Events (switch workflow)

No Search Constraints [\(Edit Search\)](#)

Connections with Application Details Table View of Connection Events

Jump to...

	First Packet	Last Packet	Action	Reason	Initiator IP	Initiator Country	Responder IP	Responder Country	Ingress Security Zone	Egress Security Zone	Source Port / ICMP Type	Destination Port / ICMP Code	Application Protocol
▼	2022-12-19 11:23:58	2022-12-19 11:24:30	Allow	Elephant Flow Exempted	172.16.77.1		172.16.4.6		inside-zone56	outside-zone56	37780 / tcp	443 (https) / tcp	HTTP
▼	2022-12-19 11:23:58		Allow	Elephant Flow Exempted	172.16.77.1		172.16.4.6		inside-zone56	outside-zone56	37780 / tcp	443 (https) / tcp	HTTP
▼	2022-12-19 11:23:58		Allow	Elephant Flow Exempted	172.16.77.1		172.16.4.6		inside-zone56	outside-zone56	37780 / tcp	443 (https) / tcp	HTTP
▼	2022-12-19 11:23:44	2022-12-19 11:23:50	Allow	Elephant Flow Exempted	172.16.77.1		172.16.4.5		inside-zone56	outside-zone56	50056 / tcp	80 (http) / tcp	HTTP
▼	2022-12-19 11:23:44		Allow	Elephant Flow Exempted	172.16.77.1		172.16.4.5		inside-zone56	outside-zone56	50056 / tcp	80 (http) / tcp	HTTP

Additional References

For detailed conceptual information, see the Elephant Flow Detection for Snort 3 chapter in this guide or the content in the following link:

- [Elephant Flow Detection](#)



CHAPTER 13

Mitigate Threats Using MITRE Framework in Snort 3 Intrusion Policies

- [About MITRE Framework, on page 145](#)
- [Benefits of MITRE Framework, on page 146](#)
- [Prerequisites, on page 146](#)
- [Sample Business Scenario, on page 146](#)
- [View and Edit Your Snort 3 Intrusion Policy, on page 146](#)
- [View Intrusion Events, on page 151](#)
- [Additional References, on page 153](#)

About MITRE Framework

The MITRE ATT&CK (Adversarial Tactics, Techniques, and Common Knowledge) Framework is an extensive knowledge base and methodology that provides insights into the tactics, techniques, and procedures (TTPs) distributed by threat actors aiming to harm systems. ATT&CK is compiled into matrices that each represent operating systems or a particular platform. Each stage of an attack, which is known as "tactics", is mapped to the specific methods used to achieve those stages, which are known as "techniques."



Note See <https://attack.mitre.org> for information about MITRE.

Each technique in the ATT&CK framework is accompanied with information about the technique, associated procedures, probable defenses and detections, and real-world examples. The MITRE ATT&CK framework also incorporates groups to refer to threat groups, activity groups, or threat actors based on the set of tactics and techniques they employ. Usage of groups in the framework helps categorize and document behaviors.

The MITRE framework enables you to navigate through your intrusion rules. MITRE is just another category of rule groups and is part of the Talos rule groups. In your Snort 3 intrusion policy, you can navigate through several levels of rule groups that provide more flexibility and logical grouping of rules.

Benefits of MITRE Framework

- MITRE Tactics, Techniques, and Procedures (TTPs) are added to intrusion events that enables administrators to act on traffic based on the MITRE ATT&CK (Adversary Tactics Techniques and Common Knowledge) framework. This enables administrators to view and handle traffic with more granularity, and they can group rules by vulnerability type, target system, or threat category.
- You can organize intrusion rules according to the MITRE ATT&CK framework. This allows you to customize policies according to specific attacker tactics and techniques.

Prerequisites

- You must be running management center 7.3.0 or later with managed devices 7.3.0 or later using Snort 3.
- You must have at least one intrusion policy. See [Create a Custom Snort 3 Intrusion Policy](#), on page 28.

Sample Business Scenario

A large corporate network uses Snort 3 as its primary intrusion detection and prevention system. In a rapidly evolving threat landscape, adoption of robust network security measures is necessary and important. Network administrators need to know if the configured policies are finding traffic of interest and if they are observing a known attack group.


As an example, you may want to know if adversaries are attempting to take advantage of a weakness in your systems or applications to cause unintended or unanticipated behavior. The weakness in the system can be a bug, a glitch, or a design vulnerability. The applications may be websites, databases, standard services, such as SMB or SSH, network device administration and management protocols, or applications, such as web servers and related services.

The insights provided by the MITRE framework enables the administrators a more precise opportunity to specify protection for specific assets and protect themselves from specific threat groups.


View and Edit Your Snort 3 Intrusion Policy

-
- Step 1** Choose **Policies > Intrusion**.
 - Step 2** Ensure that the **Intrusion Policies** tab is chosen.
 - Step 3** Click **Snort 3 Version** next to the intrusion policy that you want to view or edit.
 - Step 4** Close the Snort helper guide that pops up.
 - Step 5** Click the **Group Overrides** layer.

The **Group Overrides** layer lists all the categories of rule groups in a hierarchical structure. You can traverse to the last leaf rule group in each rule group.




Step 6 Under **Group Overrides**, ensure that **All** is chosen in the drop-down list, so that all the rule groups for the intrusion policy are visible in the left pane.



Step 7 Click **MITRE** in the left pane.

Note For this example, we have chosen MITRE, but depending on your specific requirements, you can choose the **Rule Categories** rule group or any other rule group and subsequent rule groups under it. All the rule groups use the MITRE framework.



Step 8 Under **MITRE**, click **ATT&CK Framework** to expand it.

The screenshot shows the 'Policies / Intrusion / MITRE_IPS' configuration page. The 'Base Policy' is 'Balanced Security and Connectivity' and the 'Mode' is 'Prevention'. The 'Group Overrides' section is active, showing a list of 102 items. The 'MITRE(1 group)' is expanded, and 'ATT&CK Framework(1 group)' is highlighted with a red box. The right-hand pane shows the 'MITRE' group details, including a search bar and a 'Group Name' field.

Step 9 Under **ATT&CK Framework**, click **Enterprise** to expand it.

The screenshot shows the 'Policies / Intrusion / MITRE_IPS' configuration page. The 'Group Overrides' section is active, showing a list of 102 items. The 'MITRE(1 group)' is expanded, and 'ATT&CK Framework(1 group)' is expanded, with 'Enterprise(13 groups)' highlighted by a red box. The right-hand pane shows the 'MITRE / ATT&CK Framework' group details, including a search bar and a 'Group Name' field. The 'Enterprise' group is listed with a description: 'Enterprise tactics represent the "why" of an ATT&CK technique or sub-technique. It is the adversar...'.

Step 10 Click **Edit** (✎) next to the Security Level of the rule group to make bulk changes to the security level for all the associated rule groups under the **Enterprise** rule group category.

The screenshot shows the 'Policies / Intrusion / MITRE_IPS' configuration page. The 'Group Overrides' section is active, showing a list of 102 items. The 'MITRE(1 group)' is expanded, and 'ATT&CK Framework(1 group)' is expanded, with 'Enterprise(13 groups)' expanded. The right-hand pane shows the 'MITRE / ATT&CK Framework' group details. The 'Enterprise' rule group is selected, and the 'Security Level' field is highlighted with a red box. The 'Security Level' field is currently set to 1, and the 'Edit' icon (✎) is visible next to it.

Step 11 As an example, choose security level 3 in the **Edit Security Level** window and click **Save**.

Edit Security Level ?

i Bulk Group Security Level

Impacts 34 groups. This action will change the security level of all leaf groups within this group category.

Higher security with more detections for administrators who are willing to tolerate some network latency and low level of false positives, in an effort to catch more attacks


↶ Revert to default
Cancel

Save


Step 12 Under **Enterprise**, click **Initial Access** to expand it.

Step 13 Under **Initial Access**, click **Exploit Public-Facing Application**, which is the last leaf group.


Figure 3: MITRE Tactics and Techniques




Step 14 Click the **View Rules in Rule Overrides** button to view the different rules, rule details, rule actions, and so on, for the different rules. You can change the rule actions for one or multiple rules in the **Rule Overrides** layer.

**Step 15**

Click the **Recommendations** layer and then click **Start** to start using Cisco recommended rules. You can use the intrusion rule recommendations to target vulnerabilities that are associated with host assets detected in the network. For more information, see [Generate New Secure Firewall Recommendations in Snort 3, on page 57](#).

**Step 16**

Click the **Summary** layer for a holistic view of the current changes to the policy. Based on the rule overrides, security level changes, and generation of Cisco recommended rules, you can view the rule distribution of the policy, group overrides, rule overrides, rule recommendations, and so on, to verify your changes.



What to do next


Deploy your intrusion policy to detect and log events that are triggered by the Snort rules. See [Deploy Configuration Changes](#), on page 23.

View Intrusion Events


You can view the MITRE ATT&CK techniques and rule groups in the intrusion events in the Classic Event Viewer and Unified Event Viewer. Talos provides mappings from Snort rules (GID:SID) to MITRE ATT&CK techniques and rule groups. These mappings are installed as part of the Lightweight Security Package (LSP).

Step 1 Click **Analysis > Intrusions > Events**.


Step 2 Click the **Table View of Events** tab.



Step 3 In the **MITRE ATT&CK** column header, you can see the techniques for an intrusion event.




Step 4 Click **1 Technique** to view the MITRE ATT&CK Techniques, as shown in the following figure. In this example, **Exploit Public-Facing Application** is the technique.




Step 5 Click **Close**.

Step 6 Click **Analysis > Unified Events**.


Step 7 If not already enabled, click the column selector icon to enable the **MITRE ATT&CK** and **Rule Group** columns.



Step 8 As shown in the example here, the intrusion event was triggered by an event that is mapped to one rule group. Click **1 Group** under the **Rule Group** column.



Step 9 As an example, you can view Protocol, which is the parent rule group, and DNS rule group under it.



Step 10 You can click **Protocol** to search for all the intrusion events that have at least one rule group, that is Protocol > DNS. The search results are displayed, as shown in the example below.

The screenshot shows a table of intrusion events. The 'Event Type' column is highlighted in red. A dropdown menu for 'Rule Group' is open, showing 'Protocol' and 'DNS' options. The table contains the following data:

Time	Event Type	Device	MITRE ATT&CK	Rule Group	Snort ID
2022-07-19 11:19:08	Intrusion	enc0	192.168.7.115	1 Group	1:254:16
2022-07-19 11:19:07	Intrusion	enc0	192.168.7.115	1 Group	1:254:16
2022-07-19 11:19:03	Intrusion	enc0	192.168.7.115	1 Group	1:254:16
2022-07-19 11:19:02	Intrusion	enc0	192.168.7.115	1 Group	1:254:16
2022-07-19 11:18:59	Intrusion	enc0	192.168.7.115	1 Group	1:254:16
2022-07-19 11:18:38	Intrusion	enc0	192.168.7.115	1 Group	1:254:16
2022-07-19 11:18:35	Intrusion	enc0	192.168.7.115	1 Group	1:254:16
2022-07-19 11:18:31	Intrusion	enc0	192.168.7.115	1 Group	1:254:16

Additional References

- [Intrusion Policy in Snort 3](#)
- [Edit Snort 3 Intrusion Policies, on page 29](#)
- [MITRE Information in Malware Events](#)

